



Using the Caché Callin API

Version 2018.1
2019-09-20

Using the Caché Callin API

Caché Version 2018.1 2019-09-20

Copyright © 2019 InterSystems Corporation

All rights reserved.



InterSystems, InterSystems Caché, InterSystems Ensemble, InterSystems HealthShare, HealthShare, InterSystems TrakCare, TrakCare, InterSystems DeepSee, and DeepSee are registered trademarks of InterSystems Corporation.



InterSystems IRIS Data Platform, InterSystems IRIS, InterSystems iKnow, Zen, and Caché Server Pages are trademarks of InterSystems Corporation.

All other brand or product names used herein are trademarks or registered trademarks of their respective companies or organizations.

This document contains trade secret and confidential information which is the property of InterSystems Corporation, One Memorial Drive, Cambridge, MA 02142, or its affiliates, and is furnished for the sole purpose of the operation and maintenance of the products of InterSystems Corporation. No part of this publication is to be used for any other purpose, and this publication is not to be reproduced, copied, disclosed, transmitted, stored in a retrieval system or translated into any human or computer language, in any form, by any means, in whole or in part, without the express prior written consent of InterSystems Corporation.

The copying, use and disposition of this document and the software programs described herein is prohibited except to the limited extent set forth in the standard software license agreement(s) of InterSystems Corporation covering such programs and related documentation. InterSystems Corporation makes no representations and warranties concerning such software programs other than those set forth in such standard software license agreement(s). In addition, the liability of InterSystems Corporation for any losses or damages relating to or arising out of the use of such software programs is limited in the manner set forth in such standard software license agreement(s).

THE FOREGOING IS A GENERAL SUMMARY OF THE RESTRICTIONS AND LIMITATIONS IMPOSED BY INTERSYSTEMS CORPORATION ON THE USE OF, AND LIABILITY ARISING FROM, ITS COMPUTER SOFTWARE. FOR COMPLETE INFORMATION REFERENCE SHOULD BE MADE TO THE STANDARD SOFTWARE LICENSE AGREEMENT(S) OF INTERSYSTEMS CORPORATION, COPIES OF WHICH WILL BE MADE AVAILABLE UPON REQUEST.

InterSystems Corporation disclaims responsibility for errors which may appear in this document, and it reserves the right, in its sole discretion and without notice, to make substitutions and modifications in the products and practices described in this document.

For Support questions about any InterSystems products, contact:

InterSystems Worldwide Response Center (WRC)

Tel: +1-617-621-0700

Tel: +44 (0) 844 854 2917

Email: support@InterSystems.com

Table of Contents

About This Book	1
1 The Callin Interface	3
1.1 The callin.h Header File	3
1.2 8-bit and Unicode String Handling	4
1.2.1 8-bit String Data Types	4
1.2.2 2-byte Unicode Data Types	5
1.2.3 4-byte Unicode Data Types	5
1.2.4 System-neutral Symbol Definitions	6
1.3 Using Caché Security Functions	6
1.4 Using Callin with Multithreading	6
1.4.1 Threads and UNIX® Signal Handling	7
1.5 Callin Programming Tips	9
1.5.1 Tips for All Callin Programs	9
1.5.2 Tips for Windows	10
1.5.3 Tips for UNIX®, Linux, and Mac OS	11
1.6 Running Sample Programs on Windows	11
1.7 Running Sample Programs on UNIX® and Linux	12
2 Using the Callin Functions	13
2.1 Process Control	13
2.1.1 Session Control	13
2.1.2 Running ObjectScript	14
2.2 Functions and Routines	14
2.3 Transactions and Locking	15
2.3.1 Transactions	15
2.3.2 Locking	15
2.4 Managing Objects	16
2.4.1 Orefs	16
2.4.2 Methods	16
2.4.3 Properties	17
2.5 Managing Globals	17
2.6 Managing Strings	17
2.6.1 Long String Functions	17
2.6.2 Standard String Functions	18
2.7 Managing Other Datatypes	18
3 Callin Function Reference	21
3.1 Alphabetical Function List	21
3.2 CacheAbort	24
3.3 CacheAcquireLock	25
3.4 CacheBitFind	26
3.5 CacheBitFindB	26
3.6 CacheChangePasswordA	27
3.7 CacheChangePasswordH	27
3.8 CacheChangePasswordW	28
3.9 CacheCloseOref	28
3.10 CacheContext	29
3.11 CacheConvert	29

3.12	CacheCtrl	31
3.13	CacheCvtExStrInA	31
3.14	CacheCvtExStrInW	32
3.15	CacheCvtExStrInH	33
3.16	CacheCvtExStrOutA	34
3.17	CacheCvtExStrOutW	35
3.18	CacheCvtExStrOutH	36
3.19	CacheCvtInA	37
3.20	CacheCvtInH	38
3.21	CacheCvtInW	39
3.22	CacheCvtOutA	40
3.23	CacheCvtOutH	41
3.24	CacheCvtOutW	42
3.25	CacheDoFun	43
3.26	CacheDoRtn	43
3.27	CacheEnd	44
3.28	CacheEndAll	44
3.29	CacheErrorA	45
3.30	CacheErrorH	45
3.31	CacheErrorW	46
3.32	CacheErrxlateA	47
3.33	CacheErrxlateH	47
3.34	CacheErrxlateW	48
3.35	CacheEvalA	49
3.36	CacheEvalH	49
3.37	CacheEvalW	50
3.38	CacheExecuteA	51
3.39	CacheExecuteH	52
3.40	CacheExecuteW	52
3.41	CacheExStrKill	53
3.42	CacheExStrNew	54
3.43	CacheExStrNewW	54
3.44	CacheExStrNewH	54
3.45	CacheExtFun	55
3.46	CacheGetProperty	55
3.47	CacheGlobalData	56
3.48	CacheGlobalGet	56
3.49	CacheGlobalGetBinary	57
3.50	CacheGlobalIncrement	58
3.51	CacheGlobalKill	59
3.52	CacheGlobalOrder	59
3.53	CacheGlobalQuery	60
3.54	CacheGlobalRelease	61
3.55	CacheGlobalSet	61
3.56	CacheIncrementCountOref	61
3.57	CacheInvokeClassMethod	62
3.58	CacheInvokeMethod	62
3.59	CacheOfFlush	63
3.60	CachePop	63
3.61	CachePopCvtH	63
3.62	CachePopCvtW	64

3.63 CachePopDbl	64
3.64 CachePopExStr	65
3.65 CachePopExStrCvtW	65
3.66 CachePopExStrCvtH	66
3.67 CachePopExStrW	66
3.68 CachePopExStrH	66
3.69 CachePopInt	67
3.70 CachePopInt64	67
3.71 CachePopList	68
3.72 CachePopOref	68
3.73 CachePopPtr	68
3.74 CachePopStr	69
3.75 CachePopStrH	69
3.76 CachePopStrW	70
3.77 CachePromptA	70
3.78 CachePromptH	71
3.79 CachePromptW	72
3.80 CachePushClassMethod	72
3.81 CachePushClassMethodH	73
3.82 CachePushClassMethodW	74
3.83 CachePushCvtH	75
3.84 CachePushCvtW	75
3.85 CachePushDbl	76
3.86 CachePushExStr	77
3.87 CachePushExStrCvtW	77
3.88 CachePushExStrCvtH	78
3.89 CachePushExStrW	78
3.90 CachePushExStrH	79
3.91 CachePushFunc	79
3.92 CachePushFuncH	80
3.93 CachePushFuncW	81
3.94 CachePushFuncX	82
3.95 CachePushFuncXH	83
3.96 CachePushFuncXW	84
3.97 CachePushGlobal	85
3.98 CachePushGlobalH	85
3.99 CachePushGlobalW	86
3.100 CachePushGlobalX	87
3.101 CachePushGlobalXH	87
3.102 CachePushGlobalXW	88
3.103 CachePushIEEEdbl	89
3.104 CachePushInt	89
3.105 CachePushInt64	89
3.106 CachePushList	90
3.107 CachePushLock	90
3.108 CachePushLockH	91
3.109 CachePushLockW	92
3.110 CachePushLockX	92
3.111 CachePushLockXH	93
3.112 CachePushLockXW	94
3.113 CachePushMethod	94

3.114 CachePushMethodH	95
3.115 CachePushMethodW	96
3.116 CachePushOref	96
3.117 CachePushProperty	97
3.118 CachePushPropertyH	97
3.119 CachePushPropertyW	98
3.120 CachePushPtr	99
3.121 CachePushRtn	99
3.122 CachePushRtnH	100
3.123 CachePushRtnW	101
3.124 CachePushRtnX	102
3.125 CachePushRtnXH	103
3.126 CachePushRtnXW	104
3.127 CachePushStr	105
3.128 CachePushStrH	105
3.129 CachePushStrW	106
3.130 CachePushUndef	107
3.131 CacheReleaseAllLocks	107
3.132 CacheReleaseLock	107
3.133 CacheSecureStartA	108
3.134 CacheSecureStartH	109
3.135 CacheSecureStartW	111
3.136 CacheSetDir	113
3.137 CacheSetProperty	113
3.138 CacheSignal	113
3.139 CacheSPCReceive	114
3.140 CacheSPCSend	114
3.141 CacheStartA	115
3.142 CacheStartH	116
3.143 CacheStartW	118
3.144 CacheTCommit	120
3.145 CacheTLevel	120
3.146 CacheTRollback	120
3.147 CacheTStart	121
3.148 CacheType	121
3.149 CacheUnPop	121

List of Tables

Table 2-1: Session control functions	14
Table 2-2: ObjectScript command functions	14
Table 2-3: Functions for performing function and routine calls	15
Table 2-4: Transaction functions	15
Table 2-5: Locking functions	16
Table 2-6: Oref functions	16
Table 2-7: Method functions	16
Table 2-8: Property functions	17
Table 2-9: Functions for managing globals	17
Table 2-10: Long string functions	18
Table 2-11: Standard string functions	18
Table 2-12: Other datatype functions	18

About This Book

This book describes how to use the Caché Callin API, which offers an interface that you can use from within C or C++ programs to execute Caché commands and evaluate Caché expressions.

Who This Book Is For

In order to use this book, you should be reasonably familiar with your operating system, and have significant experience with C, C++, or another language that can use the C/C++ calling standard for your operating system.

Organization of This Book

This book is organized as follows:

- The chapter “[The Callin Interface](#)” describes the Callin interface, which you can use from within C programs to execute Caché commands and evaluate Caché expressions.
- The chapter “[Using the Callin Functions](#)” provides a quick summary of the Callin functions (with links to the full description of each function) categorized according to the tasks they perform.
- The chapter “[Callin Function Reference](#)” contains detailed descriptions of all Caché Callin functions, arranged in alphabetical order.

Related Information

The Callin functions provide a very low-level programming interface. In many cases, you will be able to accomplish your objectives much more easily by using one of the standard Caché language bindings. For details, see the following sources:

- *Using C++ with Caché*
- *Using the Caché Managed Provider for .NET*
- *Using Java with Caché*

The Caché Callout Gateway is a programming interface that allows you to create a shared library with functions that can be invoked from Caché. Callout code is usually written in C or C++, but can be written in any language that supports C/C++ calling conventions.

- *Using the Caché Callout Gateway*

1

The Callin Interface

Caché offers a Callin interface you can use from within C programs to execute Caché commands and evaluate Caché expressions. This chapter describes this interface and includes the following sections:

- [The callin.h Header File](#)
- [8-bit and Unicode String Handling](#)
- [Using Caché Security Functions](#)
- [Using Callin with Multithreading](#)
- [Callin Programming Tips](#)
- [Running Sample Programs on Windows](#)
- [Running Sample Programs on UNIX® and Linux](#)

The Callin interface permits a wide variety of applications. For example, you can use it to make ObjectScript available from an integrated menu or GUI. If you gather information from an external device, such as an Automatic Teller Machine or piece of laboratory equipment, the Callin interface lets you store this data in a Caché database. Although Caché currently supports only C and C++ programs, any language that uses the calling standard for that platform (UNIX®, Windows) can invoke the Callin functions.

See [Using the Callin Functions](#) for a quick review of Callin functions. For detailed reference material on each Callin function, see the [Callin Function Reference](#).

1.1 The callin.h Header File

The callin.h header file defines prototypes for these functions, which allows your C compiler to test for valid parameter data types when you call these functions within your program. You can add this file to the list of #include statements in your C program:

```
#include "callin.h"
```

The callin.h file also contains definitions of parameter values you use in your calls, and includes various #defines that may be of use. These include operating-system-specific values, error codes, and values that determine how Caché behaves.

You can translate the distributed header file, callin.h. However, callin.h is subject to change and you must track any changes if you create a translated version of this file. InterSystems Worldwide Support Center does not handle calls about unsupported languages.

Return values and error codes

Most Callin functions return values of type `int`, where the return value does not exceed the capacity of a 16-bit integer. Returned values can be `CACHE_SUCCESS`, a Caché error, or a Callin interface error.

There are two types of errors:

- Caché errors — The return value of a Caché error is a positive integer.
- Interface errors — The return value of an interface error is 0 or a negative integer.

`callin.h` defines symbols for all Caché and interface errors, including `CACHE_SUCCESS` (0) and `CACHE_FAILURE` (-1). You can translate Caché errors (positive integers) by making a call to the Callin function **CacheErrxlate**.

1.2 8-bit and Unicode String Handling

Caché Callin functions that operate on strings have both 8-bit and Unicode versions. These functions use a suffix character to indicate the type of string that they handle:

- Names with an “A” suffix or no suffix at all (for example, **CacheEvalA** or **CachePopStr**) are versions that operate on local 8-bit encoded character strings.
- Names with a “W” suffix (for example, **CacheEvalW** or **CachePopStrW**) are versions for Unicode character strings on platforms that use 2-byte Unicode characters.
- Names with an “H” suffix (for example, **CacheEvalH** or **CachePopStrH**) are versions for Unicode character strings on platforms that use 4-byte Unicode characters.

For best performance, use the kind of string native to your installed version of Caché.

1.2.1 8-bit String Data Types

Caché supports the following data types that use local 8-bit string encoding:

- `CACHE_ASTR` — counted string of 8-bit characters
- `CACHE_ASTRP` — Pointer to an 8-bit counted string

The type definition for these is:

```
#define CACHE_MAXSTRLEN 32767
typedef struct {
    unsigned short len;
    Callin_char_t str[CACHE_MAXSTRLEN];
} CACHE_ASTR, *CACHE_ASTRP;
```

The `CACHE_ASTR` and `CACHE_ASTRP` structures contain two elements:

- `len` — An integer. When used as input, this element specifies the actual length of the string whose value is supplied in the `str` element. When used as output, this element specifies the maximum allowable length for the `str` element; upon return, this is replaced by the actual length of `str`.
- `str` — A input or output string.

`CACHE_MAXSTRLEN` is the maximum length of a string that is accepted or returned. A parameter string need not be of length `CACHE_MAXSTRLEN` nor does that much space have to be allocated in the program.

1.2.2 2–byte Unicode Data Types

Caché supports the following Unicode-related data types on platforms that use 2–byte Unicode characters:

- `CACHEWSTR` — Unicode counted string
- `CACHEWSTRP` — Pointer to Unicode counted string

The type definition for these is:

```
typedef struct {
    unsigned short len;
    unsigned short str[CACHE_MAXSTRLEN];
} CACHEWSTR, *CACHEWSTRP;
```

The `CACHEWSTR` and `CACHEWSTRP` structures contain two elements:

- `len` — An integer. When used as input, this element specifies the actual length of the string whose value is supplied in the `str` element. When used as output, this element specifies the maximum allowable length for the `str` element; upon return, this is replaced by the actual length of `str`.
- `str` — A input or output string.

`CACHE_MAXSTRLEN` is the maximum length of a string that is accepted or returned. A parameter string need not be of length `CACHE_MAXSTRLEN` nor does that much space have to be allocated in the program.

On Unicode-enabled versions of Caché, there is also the data type `CACHE_WSTRING`, which represents the native string type on 2–byte platforms. **CacheType** returns this type. Also, **CacheConvert** can specify `CACHE_WSTRING` as the data type for the return value; if this type is requested, the result is passed back as a counted Unicode string in a `CACHEWSTR` buffer.

1.2.3 4–byte Unicode Data Types

Caché supports the following Unicode-related data types on platforms that use 4–byte Unicode characters:

- `CACHEHSTR` — Extended Unicode counted string
- `CACHEHSTRP` — Pointer to Extended Unicode counted string

The type definition for these is:

```
typedef struct {
    unsigned int len;
    wchar_t str[CACHE_MAXSTRLEN];
} CACHEHSTR, *CACHEHSTRP;
```

The `CACHEHSTR` and `CACHEHSTRP` structures contain two elements:

- `len` — An integer. When used as input, this element specifies the actual length of the string whose value is supplied in the `str` element. When used as output, this element specifies the maximum allowable length for the `str` element; upon return, this is replaced by the actual length of `str`.
- `str` — A input or output string.

`CACHE_MAXSTRLEN` is the maximum length of a string that is accepted or returned. A parameter string need not be of length `CACHE_MAXSTRLEN` nor does that much space have to be allocated in the program.

On Unicode-enabled versions of Caché, there is also the data type `CACHE_HSTRING`, which represents the native string type on 4–byte platforms. **CacheType** returns this type. Also, **CacheConvert** can specify `CACHE_HSTRING` as the data type for the return value; if this type is requested, the result is passed back as a counted Unicode string in a `CACHEHSTR` buffer.

1.2.4 System-neutral Symbol Definitions

The allowed inputs and outputs of some functions vary depending on whether they are running on an 8-bit system or a Unicode system. For many of the “A” (ASCII) functions, the arguments are defined as accepting a `CACHESTR`, `CACHE_STR`, `CACHESTRP`, or `CACHE_STRP` type. These symbol definitions (without the “A”, “W”, or “H”) can conditionally be associated with either the 8-bit or Unicode names, depending on whether the symbols `CACHE_UNICODE` and `CACHE_WCHART` are defined at compile time. This way, you can write source code with neutral symbols that works with either local 8-bit or Unicode encodings.

The following excerpt from `callin.h` illustrates the concept:

```
#if defined(CACHE_UNICODE) /* Unicode character strings */
#define CACHESTR CACHEWSTR
#define CACHE_STR CACHEWSTR
#define CACHESTRP CACHEWSTRP
#define CACHE_STRP CACHEWSTRP
#define CACHE_STRING CACHE_WSTRING

#elif defined(CACHE_WCHART) /* wchar_t character strings */
#define CACHESTR CACHEHSTR
#define CACHE_STR CACHEHSTR
#define CACHESTRP CACHEHSTRP
#define CACHE_STRP CACHEHSTRP
#define CACHE_STRING CACHE_HSTRING

#else /* 8-bit character strings */
#define CACHESTR CACHE_ASTR
#define CACHE_STR CACHE_ASTR
#define CACHESTRP CACHE_ASTRP
#define CACHE_STRP CACHE_ASTRP
#define CACHE_STRING CACHE_ASTRING
#endif
```

1.3 Using Caché Security Functions

Two functions are provided for working with Caché passwords:

- **CacheSecureStart** — Similar to **CacheStart**, but with additional parameters for password authentication. The **CacheStart** function is now deprecated. If used, it will behave as if **CacheSecureStart** has been called with `NULL` for Username, Password, and ExeName. You cannot use **CacheStart** if you need to use some form of password authentication.
- **CacheChangePassword** — This function will change the user's password if they are using Caché authentication (it is not valid for LDAP/DELEGATED/Kerberos etc.). It must be called before a Callin session is initialized.

There are **CacheSecureStart** and **CacheChangePassword** functions for ASCII "A", Unicode "W", and Unicode "H" installs. The new functions either narrow, widen or "use as is" the passed in parameters, store them in the new Callin data area, then eventually call the **CacheStart** entry point.

CacheStart and **CacheSecureStart** *pin* and *pout* parameters can be passed as `NULL`, which indicates that the platform's default input and output device should be used.

1.4 Using Callin with Multithreading

Caché has been enhanced so that Callin can be used by threaded programs running under some versions of Windows and UNIX® (see “Other Supported Features” in the online *InterSystems Supported Platforms* document for this release for a list). A program can spawn multiple threads (pthreads in a UNIX® environment) and each thread can establish a separate

connection to Caché by calling **CacheSecureStart**. Threads may not share a single connection to Caché; each thread which wants to use Cache must call **CacheSecureStart**. If a thread attempts to use a Callin function and it has not called **CacheSecureStart**, a `CACHE_NOCON` error is returned.

A threaded application must link against `cachet.o` or the shared library, `cachet.so`. On UNIX® and Linux they may alternatively load the shared library dynamically. On Windows, due to the implementation of thread local storage the `cachet.dll` library cannot be dynamically loaded. The program should be careful not to exit until all of the threads which have entered Caché have called **CacheEnd** to shut down their connections. Failure to shut down each connection with **CacheEnd** may hang the instance, requiring a restart.

If **CacheSecureStart** is being used, to specify credentials as part of the login, each thread must call **CacheSecureStart** and provide the correct username/password for the connection, since credentials are not shared between the threads. There is a performance penalty within Caché using threads because of the extra code the C compiler has to generate to access thread local storage (which uses direct memory references in non-threaded builds).

A sample program, `sampcallint.c`, is provided on all platforms where this feature is supported. The `vc8` project, and the UNIX® Makefiles, include instructions to build a sample threaded Callin application on the relevant platforms.

1.4.1 Threads and UNIX® Signal Handling

On UNIX®, Caché uses a number of signals. If your application uses the same signals, you should be aware of how Caché deals with them. All signals have a default action specified by the OS. Applications may choose to leave the default action, or can choose to handle or ignore the signal. If the signal is handled, the application may further select which threads will block the signal and which threads will receive the signal. Some signals cannot be blocked, ignored, or handled. Since the default action for many signals is to halt the process, leaving the default action in place is not an option. The following signals cannot be caught or ignored, and terminate the process:

SIGNAL	DISPOSITION
SIGKILL	terminate process immediately
SIGSTOP	stop process for later resumption

The actions that an application establishes for each signal are process-wide. Whether or not the signal can be delivered to each thread is thread-specific. Each thread may specify how it will deal with signals, independently of other threads. One thread may block all signals, while another thread may allow all signals to be sent to that thread. What happens when a signal is sent to the thread depends on the process-wide handling established for that signal.

1.4.1.1 Caché Signal Processing

Caché integrates with application signal handling by saving application handlers and signal masks, then restoring them at the appropriate time. Caché processes signals in the following ways:

Generated signals

Caché installs its own signal handler for all generated signals. It saves the current (application) signal handler. If the thread catches a generated signal, the Caché signal handler disconnects the thread from Caché, calls the applications signal handling function (if any), then does `pthread_exit`.

Since signal handlers are process-wide, threads not connected to Caché will also go into the Caché handler. If Caché detects that the thread is not connected, it calls the application handler and then does `pthread_exit`.

Synchronous Signals

Caché establishes signal handlers for all synchronous signals, and unblocks these signals for each thread when the thread connects to Caché (see “[Synchronous Signals](#)” for details).

Asynchronous Signals

Caché handles all asynchronous signals that would terminate the process (see “[Asynchronous Signals](#)” for details).

Save/Restore Handlers

The system saves the signal state when the first thread connects to it. When the last thread disconnects, Caché restores the signal state for every signal that it has handled.

Save/Restore Thread Signal Mask

The thread signal mask is saved on connect, and restored when the thread disconnects.

1.4.1.2 Synchronous Signals

Synchronous signals are generated by the application itself (for example, SIGSEGV). Caché establishes signal handlers for all synchronous signals, and unblocks these signals for each thread when it connects to Caché.

Synchronous signals are caught by the thread that generated the signal. If the application has not specified a handler for a signal it has generated (for example, SIGSEGV), or if the thread has blocked the signal, then the OS will halt the entire process. If the thread enters the signal handler, that thread may exit cleanly (via `pthread_exit`) with no impact to any other thread. If a thread attempts to return from the handler, the OS will halt the entire process. The following signals cause thread termination:

SIGNAL	DISPOSITION
SIGABRT	process abort signal
SIGBUS	bus error
SIGEMT	EMT instruction
SIGFPE	floating point exception
SIGILL	illegal instruction
SIGSEGV	access violation
SIGSYS	bad argument to system call
SIGTRAP	trace trap
SIGXCPU	CPU time limit exceeded (<code>setrlimit</code>)

1.4.1.3 Asynchronous signals

Asynchronous signals are generated outside the application (for example, SIGALRM, SIGINT, and SIGTERM). Caché handles all asynchronous signals that would terminate the process.

Asynchronous signals may be caught by any thread that has not blocked the signal. The system chooses which thread to use. Any signal whose default action is to cause the process to exit must be handled, with at least one thread eligible to receive it, or else it must be specifically ignored.

The application must establish a signal handler for those signals it wants to handle, and must start a thread that does not block those signals. That thread will then be the only one eligible to receive the signal and handle it. Both the handler and the eligible thread must exist before the application makes its first call to **CacheStart**. On the first call to **CacheStart**, the following actions are performed for all asynchronous signals that would terminate the process:

- Caché looks for a handler for these signals. If a handler is found, Caché leaves it in place. Otherwise, Caché sets the signal to SIG_IGN (ignore the signal).

- Caché blocks all of these signals for connected threads, whether or not a signal has a handler. Thus, if there is a handler, only a thread that is not connected to Caché can catch the signal.

The following signals are affected by this process:

SIGNAL	DISPOSITION
SIGALRM	timer
SIGCHLD	blocked by threads
SIGDANGER	ignore if unhandled
SIGHUP	ignore if unhandled
SIGINT	ignore if unhandled
SIGPIPE	ignore if unhandled
SIGQUIT	ignore if unhandled
SIGTERM	If SIGTERM is unhandled, Caché will handle it. On receipt of a SIGTERM signal, the Caché handler will disconnect all threads and no new connections will be permitted. Handlers for SIGTERM are not stacked.
SIGUSR1	inter-process communication
SIGUSR2	inter-process communication
SIGVTALRM	virtual timer
SIGXFSZ	Caché asynchronous thread rundown

1.5 Callin Programming Tips

Topics in this section include:

- [Tips for All Callin Programs](#)
- [Tips for Windows](#)
- [Tips for UNIX®, Linux, and Mac OS](#)

1.5.1 Tips for All Callin Programs

Your external program must follow certain rules to avoid corrupting Caché data structures, which can cause a system hang.

- *Limits on the number of open files*

Your program must ensure that it does not open so many files that it prevents Caché from opening the number of databases or other files it expects to be able to. Normally, Caché looks up the user's open file quota and reserves a certain number of files for opening databases, allocating the rest for the **Open** command. Depending on the quota, Caché expects to have between 6 and 30 Caché database files open simultaneously, and from 0 to 36 files open with the **Open** command.

- *Maximum Directory Length for Callin Applications*

The directory containing any Callin application must have a full path that uses fewer than 232 characters. For example, if an application is in the `C:\CacheApps\Accounting\AccountsPayable\` directory, this has 40 characters in it and is therefore valid.

- *Call CacheEnd after CacheStart before halting*

If your Caché connection was established by a call to **CacheStart**, then you must call **CacheEnd** when you are done with the connection. You can make as many Callin function calls in between as you wish.

You must call **CacheEnd** even if the connection was broken. The connection can be broken by a call to **CacheAbort** with the **RESJOB** parameter.

CacheEnd performs cleanup operations which are necessary to prepare for another call to **CacheStart**. Calling **CacheStart** again without calling **CacheEnd** (assuming a broken connection) will return the code `CACHE_CONBROKEN`.

- *Wait until ObjectScript is done before exiting*

If you are going to exit your program, you must be certain ObjectScript has completed any outstanding request. Use the Callin function **CacheContext** to determine whether you are within ObjectScript. This call is particularly important in exit handlers and **Ctrl-C** or **Ctrl-Y** handlers. If **CacheContext** returns a non-zero value, you can invoke **CacheAbort**.

- *Maintaining Margins in Callin Sessions*

While you can set the margin within a Callin session, the margin setting is only maintained for the rest of the current command line. If a program (as with direct mode) includes the line:

```
:Use 0:10 Write x
```

the margin of 10 is established for the duration of the command line.

Certain calls affect the command line and therefore its margin. These are the calls are annotated as "calls into Caché" in the function descriptions.

- *Avoid signal handling when using CacheStart()*

CacheStart sets handlers for various signals, which may conflict with signal handlers set by the calling application.

1.5.2 Tips for Windows

These tips apply only to Windows.

- *Limitations on building Callin applications using the cache shared library (cache.dll)*

If Callin applications are built using the shared library (`cache.dll`) rather than the static object (`cache.obj`), users who have large global buffer pools may see the Callin fail to initialize (in `CacheStart`) with an error:

```
<Cache Startup Error: Mapping shared memory (203)>
```

The explanation for this lies in the behavior of system DLLs loading in Windows. Applications coded in the Win 32 API or with the Microsoft Foundation Classes (the chief libraries that support Microsoft Visual C++ development) need to have the OS load the DLLs for that Windows code as soon as they initialize. These DLLs get loaded from the top of virtual storage (higher addresses), reducing the amount of space left for the heap. On most systems, there are also a number of other DLLs (for example, DLLs supporting the display graphics) that load automatically with each Windows process at locations well above the bottom of the virtual storage. These DLLs have a tendency to request a specific address space, most commonly `0X10000000` (256MB), chopping off a few hundred megabytes of contiguous memory at the bottom of virtual memory. The result may be that there is insufficient virtual memory space in the Callin executable in which to map the Cache shared memory segment.

1.5.3 Tips for UNIX®, Linux, and Mac OS

These tips apply only to UNIX®, Linux, and Mac OS.

- *Do not disable interrupt delivery on UNIX®*

UNIX® uses interrupts. Do not prevent delivery of interrupts.

- *Use the correct version of XCode*

Versions of Caché for Mac OS X (32-bit) previous to 2010.2 were built using the Xcode 2.5 compiler. Callin programs for these versions of Caché must be built using the same compiler. If your development platform is Mac OS X 10.5 (Leopard) or later, you would have to load and use Xcode 2.5 in place of the default Xcode 3.0 compiler.

- *Avoid using reserved signals*

On UNIX®, Caché uses a number of signals. If possible, application programs linked with Caché should avoid using the following reserved signals:

SIGABRT	SIGDANGER	SIGILL	SIGQUIT	SIGTERM	SIGVTALRM
SIGALRM	SIGEMT	SIGINT	SIGSTOP	SIGTRAP	SIGXCPU
SIGBUS	SIGFPE	SIGKILL	SIGSEGV	SIGUSR1	SIGXFSZ
SIGCHLD	SIGHUP	SIGPIPE	SIGSYS	SIGUSR2	

If your application uses these signals, you should be aware of how Caché deals with them. See [Threads and UNIX® Signal Handling](#) for details.

1.6 Running Sample Programs on Windows

The `\dev\cache\callin` directory contains source files, header files, and project directories for building Caché Callin applications. These projects provide a simple demonstration of how to use some high level Caché call-in functions.

In order to build these projects, open any of the `.vcproj` files (for Visual C++ 2005), or `.dsp` files (for Visual C++ 2003). Double-click on the file, or run your Visual C++ application and select `File>Open>Project/Solution` to open the project file.

Note: You can run call-in programs on Windows 2000, but you have to compile them on Windows XP or newer, since Visual Studio 2008 and the Windows 2008 SDK only go back to Windows XP. The Visual Studio 2008 redistributables are supported on Windows 2000, but there does not appear to be a compatible compiler that is supported on Windows 2000.

The `shdir.c` file has been already initialized with the path to your Caché mgr directory. For a default installation, the `shdir.c` file will look like this:

```
char shdir[256] = "c:\\cachesys\\mgr";
```

The Callin interface provides the `CACHESETDIR` entry point to dynamically set the name of the manager directory at runtime. The shared library version of cache requires the use of this interface to find the installation's manager's directory.

Two sample C programs are provided. The `sampcallin.c` program is the standard Callin application example, and `sampcallint.c` is the thread-safe Callin application example.

There are two projects for `sampcallin.c` and a project for `sampcallint.c`. These projects are:

- `callin` — builds a statically linked Callin application using `cache.obj`.
- `callinsh` — builds a dynamically linked Callin application using `cache.dll`.
- `callint` — builds a dynamically linked thread-safe Callin application, using `cachet.dll`.

After each of the projects is built, it may be run in the Visual C++ environment.

When a project is built from the cache shared library, using `cache.dll`, the location of `cache.dll` must be defined in the user's `PATH` environment variable, except when the file is located in the current directory.

1.7 Running Sample Programs on UNIX® and Linux

The directory `dev/cache/callin/samples` contains a complete Makefile to build Callin samples. This replaces the `clink` file found in previous releases.

A shared library version of `cache` is now provided in addition to the `cache` object file. The UNIX® Makefiles build two Callin sample applications: one using the `cache` object, and one using the `libcache` shared library.

Run `make` in the `dev/cache/callin/samples` directory. The supplied Makefile will build a `cache` using the `czf` interface, a standard Callin application, and a shared library Callin application.

The file `shdir.c` is set to the appropriate value during installation, so no editing is required.

The Callin interface provides the `CACHESETDIR` entry point to dynamically set the name of the manager directory at runtime.

Using Makefiles on UNIX®

The UNIX® Makefiles for building Callin samples and customer Callin programs are run by the `make` command. `make` automatically finds the file called `Makefile` in the current directory. Thus, running `make` in the `samples` directory produces a sample Callin executable.

When invoking `make`, use the `SRC` variable to specify the name of the source program. The default is `sampcallin`. To change the name of the source file being built, override the `SRC` variable on the command line. For example, with a Callin program called `mycallin.c`, the command is:

```
make SRC=mycallin
```

Setting Permissions for Callin Executables on UNIX®

Caché executables, files, and resources such as shared memory and operating system messages, are owned by a user selected at installation time (the installation owner) and a group with a default name of `cacheusr` (you can choose a different name at installation time). These files and resources are only accessible to processes that either have this user ID or belong to this group. Otherwise, attempting to connect to Caché results in protection errors from the operating system (usually specifying that access is denied); this occurs prior to establishing any connection with Caché.

A Callin program can only run if its effective group ID is `cacheusr`. To meet this condition, one of the following must be true:

- The program is run by a user in the `cacheusr` group (or an alternate run-as group if it was changed from `cacheusr` to something else).
- The program sets its effective user or group by manipulating its `uid` or `gid` file permissions (using the UNIX® `chgrp` and `chmod` commands).

2

Using the Callin Functions

This section provides a quick summary of the Callin functions, with links to the full description of each function. The following categories are discussed:

- [Process Control](#)
These functions start and stop a Callin session, and control various settings associated with the session.
- [Functions and Routines](#)
These functions execute function or routine calls. Stack functions are provided for pushing function or routine references.
- [Transactions and Locking](#)
These functions execute the standard Caché transaction commands (TSTART, TCOMMIT, and TROLLBACK) and the LOCK command.
- [Managing Objects](#)
These functions manipulate the Oref counter, perform method calls, and get or set property values. Stack functions are also included for Orefs, method references, and property names.
- [Managing Globals](#)
These functions call into Caché to manipulate globals. Functions are provided to push globals onto the argument stack.
- [Managing Strings](#)
These functions translate strings from one form to another, and push or pop string arguments.
- [Managing Simple Datatypes](#)
These stack functions are used to push and pop arguments that have int, double, \$list, or pointer values.

The following sections discuss the individual functions in more detail.

2.1 Process Control

These functions start and stop a Callin session, control various settings associated with the session, and provide a high-level interface for executing ObjectScript commands and expressions.

2.1.1 Session Control

These functions start and stop a Callin session, and control various settings associated with the session.

Table 2–1: Session control functions

CacheAbort	Tells Caché to terminate the current request.
CacheChangePasswordA [W][H]	Changes the user's password if Caché authentication is used. Must be called before a Callin session is initialized.
CacheContext	Returns an integer indicating whether you are in a \$ZF callback session, in the Caché side of a Callin call, or in the user program side.
CacheCtrl	Determines whether or not Caché ignores CTRL-C .
CacheEnd	Terminates a Caché session and, if necessary, cleans up a broken connection. (Calls into Caché).
CacheEndAll	Disconnects all Callin threads and waits until they terminate.
CacheOflush	Flushes any pending output.
CachePromptA [W][H]	Returns a string that would be the programmer prompt.
CacheSetDir	Dynamically sets the name of the manager's directory (CacheSys\Mgr) at runtime. On Windows, the shared library version of Caché requires this function.
CacheSignal	Reports a signal detected by the user program to Caché for handling.
CacheSecureStartA [W][H]	Initiates a Caché process.
CacheStartA [W][H]	(Deprecated. Use CacheSecureStart instead) Initiates a Caché process.

2.1.2 Running ObjectScript

These functions provide a high-level interface for executing ObjectScript commands and expressions.

Table 2–2: ObjectScript command functions

CacheExecuteA [W][H]	Executes an ObjectScript command. (Calls into Caché).
CacheEvalA [W][H]	Evaluates an ObjectScript expression. (Calls into Caché).
CacheConvert	Returns the value of the Caché expression returned by CacheEval .
CacheType	Returns the datatype of an item returned by CacheEval .
CacheErrorA [W][H]	Returns the most recent error message, its associated source string, and the offset to where in the source string the error occurred.
CacheErrxlateA [W][H]	Returns the Caché error string associated with error number returned from a Callin function.

2.2 Functions and Routines

These functions call into Caché to perform function or routine calls. Functions are provided to push function or routine references onto the argument stack.

Table 2–3: Functions for performing function and routine calls

CacheDoFun	Perform a routine call (special case). (Calls into Caché).
CacheDoRtn	Perform a routine call. (Calls into Caché).
CacheExtFun	Perform an extrinsic function call. (Calls into Caché).
CachePop	Pops a value off argument stack.
CacheUnPop	Restores the stack entry from CachePop
CachePushFunc[W][H]	Pushes an extrinsic function reference onto the argument stack.
CachePushFuncX[W][H]	Push an extended function reference onto argument stack
CachePushRtn[W][H]	Push a routine reference onto argument stack
CachePushRtnX[W][H]	Push an extended routine reference onto argument stack

2.3 Transactions and Locking

These functions execute the standard Caché transaction commands (TSTART, TCOMMIT, and TROLLBACK) and the LOCK command.

2.3.1 Transactions

The following functions execute the standard Caché transaction commands.

Table 2–4: Transaction functions

CacheTCommit	Executes a Caché TCommit command.
CacheTLevel	Returns the current nesting level (\$TLEVEL) for transaction processing.
CacheTRollback	Executes a Caché TRollback command.
CacheTStart	Executes a Caché TStart command.

2.3.2 Locking

These functions execute various forms of the Cache LOCK command. Functions are provided to push lock names onto the argument stack for use by the CacheAcquireLock function.

Table 2–5: Locking functions

CacheAcquireLock	Executes a Caché LOCK command.
CacheReleaseAllLocks	Performs an argumentless Cache LOCK command to remove all locks currently held by the process.
CacheReleaseLock	Executes a Cache LOCK — command to decrement the lock count for the specified lock name.
CachePushLock[W][H]	Initializes a CacheAcquireLock command by pushing the lock name on the argument stack.
CachePushLockX[W][H]	Initializes a CacheAcquireLock command by pushing the lock name and an environment string on the argument stack.

2.4 Managing Objects

These functions call into Caché to manipulate the Oref counter, perform method calls, and get or set property values. Stack functions are also included for Orefs, method references, and property names.

2.4.1 Orefs

Table 2–6: Oref functions

CacheCloseOref	Decrement the reference counter for an OREF. (Calls into Caché).
CacheIncrementCountOref	Increment the reference counter for an OREF
CachePopOref	Pop an OREF off argument stack
CachePushOref	Push an OREF onto argument stack

2.4.2 Methods

Table 2–7: Method functions

CacheInvokeMethod	Perform an instance method call. (Calls into Caché).
CachePushMethod[W][H]	Push an instance method reference onto argument stack
CacheInvokeClassMethod	Perform a class method call. (Calls into Caché).
CachePushClassMethod[W][H]	Push a class method reference onto argument stack

2.4.3 Properties

Table 2–8: Property functions

CacheGetProperty	Obtain the value for a property. (Calls into Caché).
CacheSetProperty	Store the value for a property. (Calls into Caché).
CachePushProperty[W][H]	Push a property name onto argument stack

2.5 Managing Globals

These functions call into Caché to manipulate globals. Functions are provided to push globals onto the argument stack.

Table 2–9: Functions for managing globals

CacheGlobalGet	Obtains the value of the global reference defined by CachePushGlobal[W][H] and any subscripts. The node value is pushed onto the argument stack.
CacheGlobalGetBinary	Obtains the value of the global reference like CacheGlobalGet , and also tests to make sure that the result is a binary string that will fit in the provided buffer.
CacheGlobalSet	Stores the value of the global reference. The node value must be pushed onto the argument stack before this call.
CacheGlobalData	Performs a \$Data on the specified global.
CacheGlobalIncrement	Performs a \$Increment and returns the result on top of the stack.
CacheGlobalKill	Performs a ZKILL on a global node or tree.
CacheGlobalOrder	Performs a \$Order on the specified global.
CacheGlobalQuery	Performs a \$Query on the specified global.
CacheGlobalRelease	Releases ownership of a retained global buffer, if one exists.
CachePushGlobal[W][H]	Pushes a global name onto argument stack
CachePushGlobalX[W][H]	Pushes an extended global name onto argument stack

2.6 Managing Strings

These functions translate strings from one form to another, and push or pop string arguments.

2.6.1 Long String Functions

Caché long string functions may be used for both long strings and standard strings. Functions are provided for local 8-bit encoding, 2-byte Unicode, and 4-byte Unicode.

Table 2–10: Long string functions

CacheCvtExStrInA[W][H]	Translates a string with specified external character set encoding to the character string encoding used internally by Caché.
CacheCvtExStrOutA[W][H]	Translates a string from the character string encoding used internally in Caché to a string with the specified external character set encoding.
CacheExStrKill	Releases the storage associated with a long string.
CacheExStrNew[W][H]	Allocates the requested amount of storage for a long string, and fills in the EXSTR structure with the length and a pointer to the value field of the structure.
CachePopExStrCvtW[H]	Pops a string off the argument stack and translates it to a Unicode string.
CachePushExStrCvtW[H]	Converts a Unicode string to local 8-bit encoding and pushes it onto the argument stack.
CachePopExStr[W][H]	Pops a value off argument stack and converts it to a string of the desired type.
CachePushExStr[W][H]	Pushes a string onto the argument stack

2.6.2 Standard String Functions

The following functions deal with standard Caché strings (limited to 32K). Functions are provided for local 8-bit encoding, 2-byte Unicode, and 4-byte Unicode.

Table 2–11: Standard string functions

CacheCvtInA[W][H]	Translates a string with the specified external character set encoding to the character string encoding used internally in Caché.
CacheCvtOutA[W][H]	Translates a string from the character string encoding used internally in Caché to a string with the specified external character set encoding.
CachePopStr[W][H]	Pops a value off argument stack and converts it to a string of the desired type.
CachePushStr[W][H]	Pushes a string onto argument stack
CachePushCvtW[H]	Translates a Unicode string to local and pushes it onto argument stack
CachePopCvtW[H]	Pops a value off argument stack and translates it into the desired string type.

2.7 Managing Other Datatypes

These functions are used to push and pop argument values with datatypes such as int, double, \$list, or pointer, and to return the position of specified bit values within a bitstring.

Table 2–12: Other datatype functions

CachePushInt	Push an integer onto argument stack
---------------------	-------------------------------------

CachePopInt	Pop a value off argument stack and convert it to an integer
CachePushInt64	Push a 64-bit (long long) value onto argument stack
CachePopInt64	Pop a value off argument stack and convert it to a 64-bit (long long) value
CachePushDbI	Push a Caché double onto argument stack
CachePushIEEEDbI	Push an IEEE double onto argument stack.
CachePopDbI	Pops value off argument stack and converts it to a double
CachePushList	Translates and pushes a \$LIST object onto argument stack
CachePopList	Pops a \$LIST object off argument stack and translates it
CachePushPtr	Pushes a pointer value onto argument stack
CachePopPtr	Pops a pointer value off argument stack
CachePushUndef	Pushes an Undefined value that is interpreted as an omitted function argument.
CacheBitFind[B]	Returns the position of specified bit values within a bitstring. Similar to Caché \$BITFIND.

3

Callin Function Reference

This reference chapter contains detailed descriptions of all Caché Callin functions, arranged in alphabetical order. For an introduction to the Callin functions organized by function, see [Using the Callin Functions](#).

Note: Caché Callin functions that operate on strings have both 8-bit and Unicode versions. These functions use a suffix character to indicate the type of string that they handle:

- Names with an “A” suffix or no suffix at all (for example, [CacheEvalA](#) or [CachePopStr](#)) are versions for 8-bit character strings.
- Names with a “W” suffix (for example, [CacheEvalW](#) or [CachePopStrW](#)) are versions for Unicode character strings on platforms that use 2-byte Unicode characters.
- Names with an “H” suffix (for example, [CacheEvalH](#) or [CachePopStrH](#)) are versions for Unicode character strings on platforms that use 4-byte Unicode characters.

For convenience, the different versions of each function are listed together here. For example, [CacheEvalA\[W\]\[H\]](#) or [CachePopStr\[W\]\[H\]](#).

3.1 Alphabetical Function List

This section contains an alphabetical list of all Callin functions with a brief description of each function and links to detailed descriptions.

- [CacheAbort](#) — Tells Caché to cancel the current request being processed on the Caché side, when it is convenient to do so.
- [CacheAcquireLock](#) — Executes a Cache LOCK command. The lock reference should already be set up with [CachePushLockX\[W\]\[H\]](#).
- [CacheChangePasswordA\[W\]\[H\]](#) — Changes the user's password if Caché authentication is used (not valid for other forms of authentication).
- [CacheBitFind\[B\]](#) — Returns the position of specified bit values within a bitstring (similar to Caché \$BITFIND).
- [CacheCloseOref](#) — Decrements the system reference counter for an OREF.
- [CacheContext](#) — Returns `true` if there is a request currently being processed on the Caché side of the connection when using an external Callin program.
- [CacheConvert](#) — Converts the value returned by [CacheEvalA\[W\]\[H\]](#) into proper format and places in address specified in its return value.

- **CacheCtrl** — Determines whether or not Caché ignores **CTRL-C**.
- **CacheCvtExStrInA[W][H]** — Translates a string with specified external character set encoding to the local 8-bit character string encoding used internally only in 8-bit versions of Caché.
- **CacheCvtExStrOutA[W][H]** — Translates a string from the local 8-bit character string encoding used internally in the Caché 8-bit product to a string with the specified external character set encoding. (This is only available with 8-bit versions of Caché.)
- **CacheCvtInA[W][H]** — Translates string with specified external character set encoding to the local 8-bit character string encoding (used internally only in 8-bit versions of Caché) or the Unicode character string encoding (used internally in Unicode versions of Caché).
- **CacheCvtOutA[W][H]** — Translates a string from the local 8-bit character string encoding used internally in the Caché 8-bit product to a string with the specified external character set encoding. (This is only available with 8-bit versions of Caché.)
- **CacheDoFun** — Performs a routine call (special case).
- **CacheDoRtn** — Performs a routine call.
- **CacheEnd** — Terminates a Caché process. If there is a broken connection, it also performs clean-up operations.
- **CacheEndAll** — Disconnects all Callin threads and waits until they terminate.
- **CacheErrorA[W][H]** — Returns the most recent error message, its associated source string, and the offset to where in the source string the error occurred.
- **CacheErrxlateA[W][H]** — Translates an integer error code into a Cache error string.
- **CacheEvalA[W][H]** — Evaluates a string as if it were a Caché expression and places the return value in memory for further processing by **CacheType** and **CacheConvert**.
- **CacheExecuteA[W][H]** — Executes a command string as if it were typed at the Caché programmer prompt.
- **CacheExStrKill** — Releases the storage associated with an EXSTR string.
- **CacheExStrNew[W][H]** — Allocates the requested amount of storage for a string, and fills in the EXSTR structure with the length and a pointer to the value field of the structure.
- **CacheExtFun** — Performs an extrinsic function call where the return value is pushed onto the argument stack.
- **CacheGetProperty** — Obtains the value of the property defined by **CachePushProperty[W][H]**. The value is pushed onto the argument stack.
- **CacheGlobalData** — Performs a \$Data on the specified global.
- **CacheGlobalGet** — Obtains the value of the global reference defined by **CachePushGlobal[W][H]** and any subscripts. The node value is pushed onto the argument stack.
- **CacheGlobalIncrement** — Performs a \$INCREMENT and returns the result on top of the stack.
- **CacheGlobalKill** — Performs a ZKILL on a global node or tree.
- **CacheGlobalOrder** — Performs a \$Order on the specified global.
- **CacheGlobalQuery** — Performs a \$Query on the specified global.
- **CacheGlobalRelease** — Release ownership of a retained global buffer, if one exists.
- **CacheGlobalSet** — Stores the value of the global reference defined by **CachePushGlobal[W][H]** and any subscripts. The node value must be pushed onto the argument stack before this call.
- **CacheIncrementCountOref** — Increments the system reference counter for an OREF.

- **CacheInvokeClassMethod** — Executes the class method call defined by **CachePushClassMethod**[W][H] and any arguments. The return value is pushed onto the argument stack.
- **CacheInvokeMethod** — Executes the instance method call defined by **CachePushMethod**[W][H] and any arguments pushed onto the argument stack.
- **CacheOfflush** — Flushes any pending output.
- **CachePop** — Pops a value off argument stack.
- **CachePopCvtW**[H] — Pops a local 8-bit string off argument stack and translates it to Unicode. Identical to **CachePopStr**[W][H] for Unicode versions.
- **CachePopDbl** — Pops a value off argument stack and converts it to a double.
- **CachePopExStr**[W][H] — Pops a value off argument stack and converts it to a long string.
- **CachePopExStrCvtW**[H] — Pops a value off argument stack and converts it to a long Unicode string.
- **CachePopInt** — Pops a value off argument stack and converts it to an integer.
- **CachePopInt64** — Pops a value off argument stack and converts it to a 64-bit (long long) number.
- **CachePopList** — Pops a \$LIST object off argument stack and converts it. String elements are copied or translated as appropriate depending on whether this is a Unicode or 8-bit version.
- **CachePopOref** — Pops an OREF off argument stack.
- **CachePopPtr** — Pops a pointer off argument stack in internal format.
- **CachePopStr**[W][H] — Pops a value off argument stack and converts it to a string.
- **CachePromptA**[W][H] — Returns a string that would be the programmer prompt.
- **CachePushClassMethod**[W][H] — Pushes a class method reference onto the argument stack.
- **CachePushCvtW**[H] — Translates a Unicode string to local 8-bit and pushes it onto the argument stack. Identical to **CachePushStr**[W][H] for Unicode versions.
- **CachePushDbl** — Pushes a Caché double onto the argument stack.
- **CachePushExStr**[W][H] — Pushes a long string onto the argument stack.
- **CachePushExStrCvtW**[H] — Translates a Unicode string to local 8-bit and pushes it onto the argument stack.
- **CachePushFunc**[W][H] — Pushes an extrinsic function reference onto the argument stack.
- **CachePushFuncX**[W][H] — Pushes an extended extrinsic function reference onto the argument stack.
- **CachePushGlobal**[W][H] — Pushes a global reference onto the argument stack.
- **CachePushGlobalX**[W][H] — Pushes an extended global reference onto the argument stack.
- **CachePushIEEEEDbl** — Pushes an IEEE double onto the argument stack.
- **CachePushInt** — Pushes an integer onto the argument stack.
- **CachePushInt64** — Pushes a 64-bit (long long) number onto the argument stack.
- **CachePushList** — Converts a \$LIST object and pushes it onto the argument stack.
- **CachePushLock**[W][H] — Initializes a **CacheAcquireLock** command by pushing the lock name on the argument stack.
- **CachePushLockX**[W][H] — Initializes a **CacheAcquireLock** command by pushing the lock name and an environment string on the argument stack.
- **CachePushMethod**[W][H] — Pushes an instance method reference onto the argument stack.

- **CachePushOref** — Pushes an OREF onto the argument stack.
- **CachePushProperty[W][H]** — Pushes a property reference onto the argument stack.
- **CachePushPtr** — Pushes a pointer onto the argument stack in internal format.
- **CachePushRtn[W][H]** — Pushes a routine reference onto the argument stack.
- **CachePushRtnX[W][H]** — Pushes an extended routine reference onto the argument stack.
- **CachePushStr[W][H]** — Pushes a byte string onto the argument stack.
- **CachePushExStrCvtW[H]** — Converts a Unicode string to local 8-bit encoding and pushes it onto the argument stack.
- **CachePushUndef** — pushes an Undefined value that is interpreted as an omitted function argument.
- **CacheReleaseAllLocks** — Performs an argumentless Cache LOCK command to remove all locks currently held by the process.
- **CacheReleaseLock** — Executes a Cache LOCK command to decrement the lock count for the specified lock name. This command will only release one incremental lock at a time.
- **CacheSecureStartA[W][H]** — Calls into Cache to set up a Cache process.
- **CacheSetDir** — Dynamically sets the name of the manager's directory at runtime.
- **CacheSetProperty** — Stores the value of the property defined by **CachePushProperty[W][H]**.
- **CacheSignal** — Passes on signals caught by user's program to Caché.
- **CacheSPCReceive** — Receive single-process-communication message.
- **CacheSPCSend** — Send a single-process-communication message.
- **CacheStartA[W][H]** — Calls into Caché to set up a Caché process.
- **CacheTCommit** — Executes a Cache TCommit command.
- **CacheTLevel** — Returns the current nesting level (\$TLEVEL) for transaction processing.
- **CacheTRollback** — Executes a Cache TRollback command.
- **CacheTStart** — Executes a Cache TStart command.
- **CacheType** — Returns the native type of the item returned by **CacheEvalA[W][H]**, as the function value.
- **CacheUnPop** — Restores the stack entry from **CachePop**.

3.2 CacheAbort

```
int CacheAbort(unsigned long type)
```

Arguments

<i>type</i>	<p>Either of the following predefined values that specify how the termination occurs:</p> <ul style="list-style-type: none"> • CACHE_CTRLC — Interrupts the Caché processing as if a CTRL-C had been processed (regardless of whether CTRL-C has been enabled with CacheCtrl). A connection to Caché remains. • CACHE_RESJOB — Terminates the Callin connection. You must then call CacheEnd and then CacheStart to reconnect to Caché.
-------------	--

Description

Tells Caché to cancel the current request being processed on the Caché side, when it is convenient to do so. This function is for use if you detect some critical event in an AST (asynchronous trap) or thread running on the Callin side. (You can use **CacheContext** to determine if there is a Caché request currently being processed.) Note that this only applies to Callin programs that use an AST or separate thread.

Return Values for CacheAbort

CACHE_BADARG	The termination type is invalid.
CACHE_CONBROKEN	Connection has been broken.
CACHE_NOCON	No connection has been established.
CACHE_NOTINCACHE	The Callin partner is not in Caché at this time.
CACHE_SUCCESS	Connection formed.

Example

```
rc = CacheAbort(CACHE_CTRL);
```

3.3 CacheAcquireLock

```
int CacheAcquireLock(int nsub, int flg, int tout, int * rval)
```

Arguments

<i>nsub</i>	Number of subscripts in the lock reference.
<i>flg</i>	Modifiers to the lock command. Valid values are one or both of CACHE_INCREMENTAL_LOCK and CACHE_SHARED_LOCK.
<i>tout</i>	Number of seconds to wait for the lock command to complete. Negative for no timeout. 0 means return immediately if the lock is not available, although a minimum timeout may be applied if the lock is mapped to a remote system.
<i>rval</i>	Optional pointer to an int return value: success = 1, failure = 0.

Description

Executes a Cache LOCK command. The lock reference should already be set up with **CachePushLock**.

Return Values for CacheAcquireLock

CACHE_FAILURE	An unexpected error has occurred.
CACHE_SUCCESS	Successfully called the LOCK command (but the <i>rval</i> parameter must be examined to determine if the lock succeeded).
CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_ERARGSTACK	Argument stack overflow.

3.4 CacheBitFind

```
int CacheBitFind(int strlen, unsigned short *bitstr, int newlen, int srch, int revflg)
```

Arguments

<i>strlen</i>	Data length of the bitstring.
<i>bitstr</i>	Pointer to a Unicode bitstring.
<i>newlen</i>	0 to start at the beginning, otherwise 1-based starting position
<i>srch</i>	The bit value (0 or 1) to search for within the bitstring.
<i>revflg</i>	Specifies the search direction: 1 — Search forward (left to right) from the position indicated by <i>newlen</i> . 0 — Search backward from the position indicated by <i>newlen</i> .

Description

Returns the bit position (1-based) of the next bit within bitstring *bitstr* that has the value specified by *srch*. The direction of the search is indicated by *revflg*. Returns 0 if there are no more bits of the specified value in the specified direction.

This function is similar to Caché \$BITFIND (also see “General Information on Bitstring Functions”).

Return Values for CacheBitFind

CACHE_SUCCESS	The operation was successful.
---------------	-------------------------------

3.5 CacheBitFindB

```
int CacheBitFindB(int strlen, unsigned char *bitstr, int newlen, int srch, int revflg)
```

Arguments

<i>strlen</i>	Data length of the bitstring.
<i>bitstr</i>	Pointer to a bitstring.
<i>newlen</i>	0 to start at the beginning, otherwise 1-based starting position.
<i>srch</i>	The bit value (0 or 1) to search for within the bitstring.
<i>revflg</i>	Specifies the search direction: 1 — Search forward (left to right) from the position indicated by <i>newlen</i> . 0 — Search backward from the position indicated by <i>newlen</i> .

Description

Returns the bit position (1-based) of the next bit within bitstring *bitstr* that has the value specified by *srch*. The direction of the search is indicated by *revflg*. Returns 0 if there are no more bits of the specified value in the specified direction.

This function is similar to Caché \$BITFIND (also see “General Information on Bitstring Functions”).

Return Values for CacheBitFindB

CACHE_SUCCESS	The operation was successful.
---------------	-------------------------------

3.6 CacheChangePasswordA

Variants: [CacheChangePasswordW](#), [CacheChangePasswordH](#)

```
int CacheChangePasswordA(CACHE_ASTRP username, CACHE_ASTRP oldpassword, CACHE_ASTRP newpassword)
```

Arguments

<i>username</i>	Username of the user whose password must be changed.
<i>oldpassword</i>	User's old password.
<i>newpassword</i>	New password.

Description

This function can change the user's password if Caché authentication is used. It is not valid for LDAP, DELEGATED, Kerberos, or other forms of authentication. It must be called before a Callin session is initialized. A typical use would be to handle a CACHE_CHANGEPASSWORD error from **CacheSecureStart**. In such a case **CacheChangePassword** would be called to change the password, then **CacheSecureStart** would be called again.

Return Values for CacheChangePasswordA

CACHE_FAILURE	An unexpected error has occurred.
CACHE_SUCCESS	Password changed.

3.7 CacheChangePasswordH

Variants: [CacheChangePasswordA](#), [CacheChangePasswordW](#)

```
int CacheChangePasswordH(CACHEHSTRP username, CACHEHSTRP oldpassword, CACHEHSTRP newpassword)
```

Arguments

<i>username</i>	Username of the user whose password must be changed.
<i>oldpassword</i>	User's old password.
<i>newpassword</i>	New password.

Description

This function can change the user's password if Caché authentication is used. It is not valid for LDAP, DELEGATED, Kerberos, or other forms of authentication. It must be called before a Callin session is initialized. A typical use would be to handle a CACHE_CHANGEPASSWORD error from **CacheSecureStart**. In such a case **CacheChangePassword** would be called to change the password, then **CacheSecureStart** would be called again.

Return Values for CacheChangePasswordH

CACHE_FAILURE	An unexpected error has occurred.
CACHE_SUCCESS	Password changed.

3.8 CacheChangePasswordW

Variants: [CacheChangePasswordA](#), [CacheChangePasswordH](#)

```
int CacheChangePasswordW(CACHEWSTRP username, CACHEWSTRP oldpassword, CACHEWSTRP newpassword)
```

Arguments

<i>username</i>	Username of the user whose password must be changed.
<i>oldpassword</i>	User's old password.
<i>newpassword</i>	New password.

Description

This function can change the user's password if Caché authentication is used. It is not valid for LDAP, DELEGATED, Kerberos, or other forms of authentication. It must be called before a Callin session is initialized. A typical use would be to handle a CACHE_CHANGEPASSWORD error from **CacheSecureStart**. In such a case **CacheChangePassword** would be called to change the password, then **CacheSecureStart** would be called again.

Return Values for CacheChangePasswordW

CACHE_FAILURE	An unexpected error has occurred.
CACHE_SUCCESS	Password changed.

3.9 CacheCloseOref

```
int CacheCloseOref(unsigned int oref)
```

Arguments

<i>oref</i>	Object reference.
-------------	-------------------

Description

Decrements the system reference counter for an OREF.

Return Values for CacheCloseOref

CACHE_ERBADOREF	Invalid OREF.
CACHE_SUCCESS	The operation was successful.

3.10 CacheContext

```
int CacheContext()
```

Description

Returns an integer as the function value.

If you are using an external Callin program (as opposed to a module that was called from a **\$ZF** function) and your program employs an AST or separate thread, then **CacheContext** tells you if there is a request currently being processed on the Caché side of the connection. This information is needed to decide if you must return to Caché to allow processing to complete.

Return Values for CacheContext

-1	Created in Caché via a \$ZF callback.
0	No connection or not in Caché at the moment.
1	In Caché via an external (i.e., not \$ZF) connection. An asynchronous trap (AST), such as an exit-handler, would need to return to Caché to allow Caché to complete processing.

Note: The information about whether you are in a **\$ZF** function from a program or an AST is needed because, if you are in an AST, then you need to return to Caché to allow processing to complete.

Example

```
rc = CacheContext();
```

3.11 CacheConvert

```
int CacheConvert(unsigned long type, void * rbuf)
```

Arguments

<i>type</i>	The #define'd type, with valid values listed below.
<i>rbuf</i>	Address of a data area of the proper size for the data type. If the type is <code>CACHE_ASTRING</code> , <i>rbuf</i> should be the address of a <code>CACHE_ASTR</code> structure that will contain the result, and the <i>len</i> element in the structure should be filled in to represent the maximum size of the string to be returned (in characters). Similarly, if the type is <code>CACHE_WSTRING</code> , <i>rbuf</i> should be the address of a <code>CACHEWSTR</code> structure whose <i>len</i> element has been filled in to represent the maximum size (in characters).

Description

Converts the value returned by **CacheEval** into proper format and places in address specified in its return value (listed below as *rbuf*).

Valid values of *type* are:

- `CACHE_ASTRING` — 8-bit character string.
- `CACHE_CHAR` — 8-bit signed integer.

- CACHE_DOUBLE — 64-bit floating point.
- CACHE_FLOAT — 32-bit floating point.
- CACHE_INT — 32-bit signed integer.
- CACHE_INT2 — 16-bit signed integer.
- CACHE_INT4 — 32-bit signed integer.
- CACHE_INT8 — 64-bit signed integer.
- CACHE_UCHAR — 8-bit unsigned integer.
- CACHE_UINT — 32-bit unsigned integer.
- CACHE_UINT2 — 16-bit unsigned integer.
- CACHE_UINT4 — 32-bit unsigned integer.
- CACHE_UINT8 — 64-bit unsigned integer.
- CACHE_WSTRING — Unicode character string.

Return Values for CacheConvert

CACHE_BADARG	Type is invalid.
CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_ERSYSTEM	Either ObjectScript generated a <SYSTEM> error, or if called from a \$ZF function, an internal counter may be out of sync.
CACHE_FAILURE	An unexpected error has occurred.
CACHE_NOCON	No connection has been established.
CACHE_NORES	No result whose type can be returned (no call to CacheEvalA preceded this call).
CACHE_RETTRUNC	Success, but the type CACHE_ASTRING, CACHE_INT8, CACHE_UINT8 and CACHE_WSTRING resulted in a value that would not fit in the space allocated in <i>retval</i> . For CACHE_INT8 and CACHE_UINT8, this means that the expression resulted in a floating point number that could not be normalized to fit within 64 bits.
CACHE_STRTOOLONG	String is too long.
CACHE_SUCCESS	Value returned by last CacheEval converted successfully.

Note: Caché may perform division when calculating the return value for floating point types, CACHE_FLOAT and CACHE_DOUBLE, which have decimal parts (including negative exponents), as well as the 64-bit integer types (CACHE_INT8 and CACHE_UINT8). Therefore, the returned result may not be identical in value to the original. CACHE_ASTRING, CACHE_INT8, CACHE_UINT8 and CACHE_WSTRING can return the status CACHE_RETTRUNC.

Example

```

CACHE_ASTR retval;
/* define variable retval */

retval.len = 20;
/* maximum return length of string */

rc = CacheConvert(CACHE_ASTRING,&retval);
    
```

3.12 CacheCtrl

```
int CacheCtrl(unsigned long flags)
```

Arguments

<i>flags</i>	Either of two #define'd values specifying how Caché handles certain keystrokes.
--------------	---

Description

Determines whether or not Caché ignores CTRL-C. *flags* can have bit state values of

- `CACHE_DISACTRLC` — Caché ignores CTRL-C.
- `CACHE_ENABCTRLC` — Default if function is not called, unless overridden by a **BREAK** or an **OPEN** command. In Caché, CTRL-C generates an <INTERRUPT>.

Return Values for CacheCtrl

<code>CACHE_FAILURE</code>	Returns if called from a \$ZF function (rather than from within a Callin executable).
<code>CACHE_SUCCESS</code>	Control function performed.

Example

```
rc = CacheCtrl(CACHE_ENABCTRLC);
```

3.13 CacheCvtExStrInA

Variants: [CacheCvtExStrInW](#), [CacheCvtExStrInH](#)

```
int CacheCvtExStrInA(CACHE_EXSTRP src, CACHE_ASTRP tbl, CACHE_EXSTRP res)
```

Arguments

<i>src</i>	Address of a <code>CACHE_EXSTRP</code> variable that contains the string to be converted.
<i>tbl</i>	The name of the I/O translation table to use to perform the translation (a null string indicates that the default process I/O translation table name should be used).
<i>res</i>	Address of a <code>CACHE_EXSTRP</code> variable that will contain the result.

Description

Translates a string with specified external character set encoding to the local 8-bit character string encoding used internally only in 8-bit versions of Caché.

Return Values for CacheCvtExStrInA

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_ERRUNIMPLEMENTED	Not available for Unicode.
CACHE_ERVALUE	The specified I/O translation table name was undefined or did not have an input component.
CACHE_ERXLATE	Input string could not be translated using the specified I/O translation table.
CACHE_NOCON	No connection has been established.
CACHE_RETTRUNC	Result was truncated because result buffer was too small.
CACHE_FAILURE	Error encountered while trying to build translation data structures (probably not enough partition memory).
CACHE_SUCCESS	Translation completed successfully.

3.14 CacheCvtExStrInW

Variants: [CacheCvtExStrInA](#), [CacheCvtExStrInH](#)

```
int CacheCvtExStrInW(CACHE_EXSTRP src, CACHEWSTRP tbl, CACHE_EXSTRP res)
```

Arguments

<i>src</i>	Address of a CACHE_EXSTRP variable that contains the string to be converted.
<i>tbl</i>	The name of the I/O translation table to use to perform the translation (a null string indicates that the default process I/O translation table name should be used).
<i>res</i>	Address of a CACHE_EXSTRP variable that will contain the result.

Description

Translates a string with specified external character set encoding to the 2-byte Unicode character string encoding used internally in Unicode versions of Caché.

Return Values for CacheCvtExStrInW

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_ERRUNIMPLEMENTED	Not available for 8-bit systems.
CACHE_ERVALUE	The specified I/O translation table name was undefined or did not have an input component.
CACHE_ERXLATE	Input string could not be translated using the specified I/O translation table.
CACHE_NOCON	No connection has been established.
CACHE_RETTRUNC	Result was truncated because result buffer was too small.
CACHE_FAILURE	Error encountered while trying to build translation data structures (probably not enough partition memory).
CACHE_SUCCESS	Translation completed successfully.

3.15 CacheCvtExStrInH

Variants: [CacheCvtExStrInA](#), [CacheCvtExStrInW](#)

```
int CacheCvtExStrInH(CACHE_EXSTRP src, CACHEWSTRP tbl, CACHE_EXSTRP res)
```

Arguments

<i>src</i>	Address of a CACHE_EXSTRP variable that contains the string to be converted.
<i>tbl</i>	The name of the I/O translation table to use to perform the translation (a null string indicates that the default process I/O translation table name should be used).
<i>res</i>	Address of a CACHE_EXSTRP variable that will contain the result.

Description

Translates a string with specified external character set encoding to the 4-byte Unicode character string encoding used internally in Unicode versions of Caché.

Return Values for CacheCvtExStrInH

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_ERRUNIMPLEMENTED	Not available for 8-bit systems.
CACHE_ERVALUE	The specified I/O translation table name was undefined or did not have an input component.
CACHE_ERXLATE	Input string could not be translated using the specified I/O translation table.
CACHE_NOCON	No connection has been established.
CACHE_RETTRUNC	Result was truncated because result buffer was too small.
CACHE_FAILURE	Error encountered while trying to build translation data structures (probably not enough partition memory).
CACHE_SUCCESS	Translation completed successfully.

3.16 CacheCvtExStrOutA

Variants: [CacheCvtExStrOutW](#), [CacheCvtExStrOutH](#)

```
int CacheCvtExStrOutA(CACHE_EXSTRP src, CACHE_ASTRP tbl, CACHE_EXSTRP res)
```

Arguments

<i>src</i>	Address of a CACHE_EXSTRP variable that contains the string to be converted.
<i>tbl</i>	The name of the I/O translation table to use to perform the translation (a null string indicates that the default process I/O translation table name should be used).
<i>res</i>	Address of a CACHE_EXSTRP variable that will contain the result.

Description

Translates a string from the local 8-bit character string encoding used internally in the Caché 8-bit product to a string with the specified external character set encoding. (This is only available with 8-bit versions of Caché.)

Return Values for CacheCvtExStrOutA

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_ERRUNIMPLEMENTED	Not available for Unicode.
CACHE_ERVALUE	The specified I/O translation table name was undefined or did not have an input component.
CACHE_ERXLATE	Input string could not be translated using the specified I/O translation table.
CACHE_NOCON	No connection has been established.
CACHE_RETTRUNC	Result was truncated because result buffer was too small.
CACHE_FAILURE	Error encountered while trying to build translation data structures (probably not enough partition memory).
CACHE_SUCCESS	Translation completed successfully.

3.17 CacheCvtExStrOutW

Variants: [CacheCvtExStrOutA](#), [CacheCvtExStrOutH](#)

```
int CacheCvtExStrOutW(CACHE_EXSTRP src, CACHEWSTRP tbl, CACHE_EXSTRP res)
```

Arguments

<i>src</i>	Address of a CACHE_EXSTRP variable that contains the string to be converted.
<i>tbl</i>	The name of the I/O translation table to use to perform the translation (a null string indicates that the default process I/O translation table name should be used).
<i>res</i>	Address of a CACHE_EXSTRP variable that will contain the result.

Description

Translates a string from the 2-byte Unicode character string encoding used internally in Unicode versions of Caché to a string with the specified external character set encoding. (This is only available with Unicode versions of Caché.)

Return Values for CacheCvtExStrOutW

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_ERRUNIMPLEMENTED	Not available for 8-bit systems.
CACHE_ERVALUE	The specified I/O translation table name was undefined or did not have an input component.
CACHE_ERXLATE	Input string could not be translated using the specified I/O translation table.
CACHE_NOCON	No connection has been established.
CACHE_RETTRUNC	Result was truncated because result buffer was too small.
CACHE_FAILURE	Error encountered while trying to build translation data structures (probably not enough partition memory).
CACHE_SUCCESS	Translation completed successfully.

3.18 CacheCvtExStrOutH

Variants: [CacheCvtExStrOutA](#), [CacheCvtExStrOutW](#)

```
int CacheCvtExStrOutH(CACHE_EXSTRP src, CACHEWSTRP tbl, CACHE_EXSTRP res)
```

Arguments

<i>src</i>	Address of a CACHE_EXSTRP variable that contains the string to be converted.
<i>tbl</i>	The name of the I/O translation table to use to perform the translation (a null string indicates that the default process I/O translation table name should be used).
<i>res</i>	Address of a CACHE_EXSTRP variable that will contain the result.

Description

Translates a string from the 4-byte Unicode character string encoding used internally in Unicode versions of Caché to a string with the specified external character set encoding. (This is only available with Unicode versions of Caché.)

Return Values for CacheCvtExStrOutH

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_ERRUNIMPLEMENTED	Not available for 8-bit systems.
CACHE_ERVALUE	The specified I/O translation table name was undefined or did not have an input component.
CACHE_ERXLATE	Input string could not be translated using the specified I/O translation table.
CACHE_NOCON	No connection has been established.
CACHE_RETTRUNC	Result was truncated because result buffer was too small.
CACHE_FAILURE	Error encountered while trying to build translation data structures (probably not enough partition memory).
CACHE_SUCCESS	Translation completed successfully.

3.19 CacheCvtInA

Variants: [CacheCvtInW](#), [CacheCvtInH](#)

```
int CacheCvtInA(CACHE_ASTRP src, CACHE_ASTRP tbl, CACHE_ASTRP res)
```

Arguments

<i>src</i>	The string in an external character set encoding to be translated (described using a counted character string buffer). The string should be initialized, for example, by setting the value to the number of blanks representing the maximum number of characters expected as output.
<i>tbl</i>	The name of the I/O translation table to use to perform the translation (a null string indicates that the default process I/O translation table name should be used).
<i>res</i>	Address of a CACHE_ASTR variable that will contain the counted 8-bit string result.

Description

Translates string with specified external character set encoding to the local 8-bit character string encoding used internally only in 8-bit versions of Caché.

Return Values for CacheCvtInA

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_ERRUNIMPLEMENTED	Not available for Unicode.
CACHE_ERVALUE	The specified I/O translation table name was undefined or did not have an input component.
CACHE_ERXLATE	Input string could not be translated using the specified I/O translation table.
CACHE_NOCON	No connection has been established.
CACHE_RETTRUNC	Result was truncated because result buffer was too small.
CACHE_FAILURE	Error encountered while trying to build translation data structures (probably not enough partition memory).
CACHE_SUCCESS	Translation completed successfully.

3.20 CacheCvtInH

Variants: [CacheCvtInA](#), [CacheCvtInW](#)

```
int CacheCvtInH(CACHE_ASTRP src, CACHEHSTRP tbl, CACHEHSTRP res)
```

Arguments

<i>src</i>	The string in an external character set encoding to be translated (described using the number of bytes required to hold the Unicode string).
<i>tbl</i>	The name of the I/O translation table to use to perform the translation (a null string indicates that the default process I/O translation table name should be used).
<i>res</i>	Address of a CACHEHSTRP variable that will contain the counted Unicode string result.

Description

Translates string with specified external character set encoding to the Unicode character string encoding used internally in Unicode versions of Caché.

Return Values for CacheCvtInH

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_ERRUNIMPLEMENTED	Not available for 8-bit systems.
CACHE_ERVALUE	The specified I/O translation table name was undefined or did not have an input component.
CACHE_ERXLATE	Input string could not be translated using the specified I/O translation table.
CACHE_NOCON	No connection has been established.
CACHE_RETTRUNC	Result was truncated because result buffer was too small.
CACHE_FAILURE	Error encountered while trying to build translation data structures (probably not enough partition memory).
CACHE_SUCCESS	Translation completed successfully.

3.21 CacheCvtInW

Variants: [CacheCvtInA](#), [CacheCvtInH](#)

```
int CacheCvtInW(CACHE_ASTRP src, CACHEWSTRP tbl, CACHEWSTRP res)
```

Arguments

<i>src</i>	The string in an external character set encoding to be translated (described using the number of bytes required to hold the Unicode string).
<i>tbl</i>	The name of the I/O translation table to use to perform the translation (a null string indicates that the default process I/O translation table name should be used).
<i>res</i>	Address of a CACHEWSTR variable that will contain the counted Unicode string result.

Description

Translates string with specified external character set encoding to the Unicode character string encoding used internally in Unicode versions of Caché.

Return Values for CacheCvtInW

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_ERRUNIMPLEMENTED	Not available for 8-bit systems.
CACHE_ERVALUE	The specified I/O translation table name was undefined or did not have an input component.
CACHE_ERXLATE	Input string could not be translated using the specified I/O translation table.
CACHE_NOCON	No connection has been established.
CACHE_RETTRUNC	Result was truncated because result buffer was too small.
CACHE_FAILURE	Error encountered while trying to build translation data structures (probably not enough partition memory).
CACHE_SUCCESS	Translation completed successfully.

3.22 CacheCvtOutA

Variants: [CacheCvtOutW](#), [CacheCvtOutH](#)

```
int CacheCvtOutA(CACHE_ASTRP src, CACHE_ASTRP tbl, CACHE_ASTRP res)
```

Arguments

<i>src</i>	The string in the local 8-bit character string encoding used internally in the Caché 8-bit product (if a NULL pointer is passed, Caché will use the result from the last call to CacheEvalA or CacheEvalW).
<i>tbl</i>	The name of the I/O translation table to use to perform the translation (a null string indicates that the default process I/O translation table name should be used).
<i>res</i>	Address of a CACHE_ASTR variable that will contain the result in the target external character set encoding (described using a counted 8-bit character string buffer).

Description

Translates a string from the local 8-bit character string encoding used internally in the Caché 8-bit product to a string with the specified external character set encoding. (This is only available with 8-bit versions of Caché.)

Return Values for CacheCvtOutA

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_ERRUNIMPLEMENTED	Not available for Unicode.
CACHE_ERVALUE	The specified I/O translation table name was undefined or did not have an input component.
CACHE_ERXLATE	Input string could not be translated using the specified I/O translation table.
CACHE_NOCON	No connection has been established.
CACHE_RETTRUNC	Result was truncated because result buffer was too small.
CACHE_FAILURE	Error encountered while trying to build translation data structures (probably not enough partition memory).
CACHE_SUCCESS	Translation completed successfully.

3.23 CacheCvtOutH

Variants: [CacheCvtOutA](#), [CacheCvtOutW](#)

```
int CacheCvtOutH(CACHEHSTRP src, CACHEHSTRP tbl, CACHE_ASTRP res)
```

Arguments

<i>src</i>	The string in the Unicode character string encoding used internally in the Caché Unicode product (if a NULL pointer is passed, Caché will use the result from the last call to CacheEvalA or CacheEvalW).
<i>tbl</i>	The name of the I/O translation table to use to perform the translation (a null string indicates that the default process I/O translation table name should be used).
<i>res</i>	Address of a CACHE_ASTR variable that will contain the result in the target external character set encoding (described using a counted 8-bit character string buffer).

Description

Translates a string from the Unicode character string encoding used internally in Unicode versions of Caché to a string with the specified external character set encoding. (This is only available with Unicode versions of Caché.)

Return Values for CacheCvtOutH

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_ERRUNIMPLEMENTED	Not available for 8-bit systems.
CACHE_ERVALUE	The specified I/O translation table name was undefined or did not have an input component.
CACHE_ERXLATE	Input string could not be translated using the specified I/O translation table.
CACHE_NOCON	No connection has been established.
CACHE_RETTRUNC	Result was truncated because result buffer was too small.
CACHE_FAILURE	Error encountered while trying to build translation data structures (probably not enough partition memory).
CACHE_SUCCESS	Translation completed successfully.

3.24 CacheCvtOutW

Variants: [CacheCvtOutA](#), [CacheCvtOutH](#)

```
int CacheCvtOutW(CACHEWSTRP src, CACHEWSTRP tbl, CACHE_ASTRP res)
```

Arguments

<i>src</i>	The string in the Unicode character string encoding used internally in the Caché Unicode product (if a NULL pointer is passed, Caché will use the result from the last call to CacheEvalA or CacheEvalW).
<i>tbl</i>	The name of the I/O translation table to use to perform the translation (a null string indicates that the default process I/O translation table name should be used).
<i>res</i>	Address of a CACHE_ASTR variable that will contain the result in the target external character set encoding (described using a counted 8-bit character string buffer).

Description

Translates a string from the Unicode character string encoding used internally in Unicode versions of Caché to a string with the specified external character set encoding. (This is only available with Unicode versions of Caché.)

Return Values for CacheCvtOutW

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_ERRUNIMPLEMENTED	Not available for 8-bit systems.
CACHE_ERVALUE	The specified I/O translation table name was undefined or did not have an input component.
CACHE_ERXLATE	Input string could not be translated using the specified I/O translation table.
CACHE_NOCON	No connection has been established.
CACHE_RETTRUNC	Result was truncated because result buffer was too small.
CACHE_FAILURE	Error encountered while trying to build translation data structures (probably not enough partition memory).
CACHE_SUCCESS	Translation completed successfully.

3.25 CacheDoFun

```
int CacheDoFun(unsigned int flags, int nargs)
```

Arguments

<i>flags</i>	Routine flags from CachePushRtn[XW]
<i>narg</i>	Number of call arguments pushed onto the argument stack. Target must have a (possibly empty) formal parameter list.

Description

Performs a routine call (special case).

Return Values for CacheDoFun

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_FAILURE	Internal consistency error.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.26 CacheDoRtn

```
int CacheDoRtn(unsigned int flags, int nargs)
```

Arguments

<i>flags</i>	Routine flags from CachePushRtn[XW]
<i>narg</i>	Number of call arguments pushed onto the argument stack. If zero, target must not have a formal parameter list.

Description

Performs a routine call.

Return Values for CacheDoRtn

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_FAILURE	Internal consistency error.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.27 CacheEnd

```
int CacheEnd()
```

Description

Terminates a Caché process. If there is a broken connection, it also performs clean-up operations.

Return Values for CacheEnd

CACHE_FAILURE	Returns if called from a \$ZF function (rather than from within a Callin executable).
CACHE_NOCON	No connection has been established.
CACHE_SUCCESS	Caché session terminated/cleaned up.

CacheEnd can also return any of the Caché error codes.

Example

```
rc = CacheEnd();
```

3.28 CacheEndAll

```
int CacheEndAll()
```

Description

Disconnects all threads in a threaded Callin environment, then schedules the threads for termination and waits until they are done.

Return Values for CacheEndAll

CACHE_SUCCESS	Caché session terminated/cleaned up.
---------------	--------------------------------------

Example

```
rc = CacheEndAll();
```

3.29 CacheErrorA

Variants: [CacheErrorW](#), [CacheErrorH](#)

```
int CacheErrorA(CACHE_ASTRP msg, CACHE_ASTRP src, int * offp)
```

Arguments

<i>msg</i>	The error message or the address of a variable to receive the error message.
<i>src</i>	The source string for the error or the address of a variable to receive the source string the error message.
<i>offp</i>	An integer that specifies the offset to location in <i>errsrc</i> or the address of an integer to receive the offset to the source string the error message.

Description

Returns the most recent error message, its associated source string, and the offset to where in the source string the error occurred.

Return Values for CacheErrorA

CACHE_CONBROKEN	Connection has been broken.
CACHE_NOCON	No connection has been established.
CACHE_RETTOOSMALL	The length of the return value for either <i>errmsg</i> or <i>errsrc</i> was not of the valid size.
CACHE_SUCCESS	Connection formed.

Example

```
CACHE_ASTR errmsg;
CACHE_ASTR srcline;
int offset;
errmsg.len = 50;
srcline.len = 100;
if ((rc = CacheErrorA(&errmsg, &srcline, &offset)) != CACHE_SUCCESS)
printf("\r\nfailed to display error - rc = %d",rc);
```

3.30 CacheErrorH

Variants: [CacheErrorA](#), [CacheErrorW](#)

```
int CacheErrorH(CACHEHSTRP msg, CACHEHSTRP src, int * offp)
```

Arguments

<i>msg</i>	The error message or the address of a variable to receive the error message.
<i>src</i>	The source string for the error or the address of a variable to receive the source string the error message.
<i>offp</i>	The offset to location in <i>errsrc</i> or the address of an integer to receive the offset to the source string the error message.

Description

Returns the most recent error message, its associated source string, and the offset to where in the source string the error occurred.

Return Values for CacheErrorH

CACHE_CONBROKEN	Connection has been broken.
CACHE_NOCON	No connection has been established.
CACHE_RETTOOSMALL	The length of the return value for either <i>errmsg</i> or <i>errsrc</i> was not of the valid size.
CACHE_SUCCESS	Connection formed.

Example

```
CACHEHSTRP errmsg;
CACHEHSTRP srcline;
int offset;
errmsg.len = 50;
srcline.len = 100;
if ((rc = CacheErrorH(&errmsg, &srcline, &offset)) != CACHE_SUCCESS)
printf("\r\nfailed to display error - rc = %d",rc);
```

3.31 CacheErrorW

Variants: [CacheErrorA](#), [CacheErrorH](#)

```
int CacheErrorW(CACHEWSTRP msg, CACHEWSTRP src, int * offp)
```

Arguments

<i>msg</i>	The error message or the address of a variable to receive the error message.
<i>src</i>	The source string for the error or the address of a variable to receive the source string the error message.
<i>offp</i>	The offset to location in <i>errsrc</i> or the address of an integer to receive the offset to the source string the error message.

Description

Returns the most recent error message, its associated source string, and the offset to where in the source string the error occurred.

Return Values for CacheErrorW

CACHE_CONBROKEN	Connection has been broken.
CACHE_NOCON	No connection has been established.
CACHE_RETTOOSMALL	The length of the return value for either <i>errmsg</i> or <i>errsrc</i> was not of the valid size.
CACHE_SUCCESS	Connection formed.

Example

```
CACHEWSTRP errmsg;
CACHEWSTRP srcline;
int offset;
errmsg.len = 50;
srcline.len = 100;
if ((rc = CacheErrorW(&errmsg, &srcline, &offset)) != CACHE_SUCCESS)
printf("\r\nfailed to display error - rc = %d",rc);
```

3.32 CacheErrxlateA

Variants: [CacheErrxlateW](#), [CacheErrxlateH](#)

```
int CacheErrxlateA(int code, CACHE_ASTRP rbuf)
```

Arguments

<i>code</i>	The error code.
<i>rbuf</i>	Address of a CACHE_ASTR variable to contain the Caché error string. The <i>len</i> field should be loaded with the maximum string size that can be returned.

Description

Translates error code *code* into a Cache error string, and writes that string into the structure pointed to by *rbuf*

Return Values for CacheErrxlateA

CACHE_ERUNKNOWN	The specified code is less than 1 (in the range of the Callin interface errors) or is above the largest Caché error number.
CACHE_RETTRUNC	The associated error string was truncated to fit in the allocated area.
CACHE_SUCCESS	Connection formed.

Example

```
CACHE_ASTR retval; /* define variable retval */
retval.len = 30; /* maximum return length of string */
rc = CacheErrxlateA(CACHE_ERSTORE,&retval);
```

3.33 CacheErrxlateH

Variants: [CacheErrxlateA](#), [CacheErrxlateW](#)

```
int CacheErrxlateH(int code, CACHEHSTRP rbuf)
```

Arguments

<i>code</i>	The error code.
<i>rbuf</i>	Address of a CACHEHSTRP variable to contain the Caché error string. The <i>len</i> field should be loaded with the maximum string size that can be returned.

Description

Translates error code *code* into a Cache error string, and writes that string into the structure pointed to by *rbuf*

Return Values for CacheErrxlateH

CACHE_ERUNKNOWN	The specified code is less than 1 (in the range of the Callin interface errors) or is above the largest Caché error number.
CACHE_RETTRUNC	The associated error string was truncated to fit in the allocated area.
CACHE_SUCCESS	Connection formed.

Example

```
CACHEHSTR retval; /* define variable retval */
retval.len = 30; /* maximum return length of string */
rc = CacheErrxlateH(CACHE_ERSTORE,&retval);
```

3.34 CacheErrxlateW

Variants: [CacheErrxlateA](#), [CacheErrxlateH](#)

```
int CacheErrxlateW(int code, CACHEWSTRP rbuf)
```

Arguments

<i>code</i>	The error code.
<i>rbuf</i>	Address of a CACHEWSTRP variable to contain the Caché error string. The <i>len</i> field should be loaded with the maximum string size that can be returned.

Description

Translates error code *code* into a Cache error string, and writes that string into the structure pointed to by *rbuf*

Return Values for CacheErrxlateW

CACHE_ERUNKNOWN	The specified code is less than 1 (in the range of the Callin interface errors) or is above the largest Caché error number.
CACHE_RETTRUNC	The associated error string was truncated to fit in the allocated area.
CACHE_SUCCESS	Connection formed.

Example

```
CACHEWSTR retval; /* define variable retval */
retval.len = 30; /* maximum return length of string */
rc = CacheErrxlateW(CACHE_ERSTORE,&retval);
```

3.35 CacheEvalA

Variants: [CacheEvalW](#), [CacheEvalH](#)

```
int CacheEvalA(CACHE_ASTRP volatile expr)
```

Arguments

<i>expr</i>	The address of a CACHE_ASTR variable.
-------------	---------------------------------------

Description

Evaluates a string as if it were a Caché expression and places the return value in memory for further processing by **CacheType** and **CacheConvert**.

If **CacheEvalA** completes successfully, it sets a flag that allows calls to **CacheType** and **CacheConvert** to complete. These functions are used to process the item returned from **CacheEvalA**.

CAUTION: The next call to **CacheEvalA**, **CacheExecuteA**, or **CacheEnd** will overwrite the existing return value.

Return Values for CacheEvalA

CACHE_CONBROKEN	Connection has been closed due to a serious error condition or RESJOB .
CACHE_ERSYSTEM	Either Caché generated a <SYSTEM> error, or if called from a \$ZF function, an internal counter may be out of sync.
CACHE_NOCON	No connection has been established.
CACHE_STRTOOLONG	String is too long.
CACHE_SUCCESS	String evaluated successfully.

CacheEvalA can also return any of the Caché error codes.

Example

```
int rc;
CACHE_ASTR retval;
CACHE_ASTR expr;

strcpy(expr.str, "\"Record\"_\"^Recnum\" = \"_$$^GetRec(^Recnum)\");
expr.len = strlen(expr.str);
rc = CacheEvalA(&expr);
if (rc == CACHE_SUCCESS)
    rc = CacheConvert(CACHE_ASTRING, &retval);
```

3.36 CacheEvalH

Variants: [CacheEvalA](#), [CacheEvalW](#)

```
int CacheEvalH(CACHEHSTRP volatile expr)
```

Arguments

<i>expr</i>	The address of a CACHEHSTRP variable.
-------------	---------------------------------------

Description

Evaluates a string as if it were a Caché expression and places the return value in memory for further processing by **CacheType** and **CacheConvert**.

If **CacheEvalH** completes successfully, it sets a flag that allows calls to **CacheType** and **CacheConvert** to complete. These functions are used to process the item returned from **CacheEvalA**.

CAUTION: The next call to **CacheEvalH**, **CacheExecuteH**, or **CacheEnd** will overwrite the existing return value.

Return Values for CacheEvalH

CACHE_CONBROKEN	Connection has been closed due to a serious error condition or RESJOB .
CACHW_ERSYSTEM	Either Caché generated a <SYSTEM> error, or if called from a \$ZF function, an internal counter may be out of sync.
CACHE_NOCON	No connection has been established.
CACHE_STRTOOLONG	String is too long.
CACHE_SUCCESS	String evaluated successfully.

CacheEvalH can also return any of the Caché error codes.

Example

```
int rc;
CACHEHSTRP retval;
CACHEHSTRP expr;

strcpy(expr.str, "\"Record\"_^Recnum\_\" = \"_$$^GetRec(^Recnum)\");
expr.len = strlen(expr.str);
rc = CacheEvalH(&expr);
if (rc == CACHE_SUCCESS)
    rc = CacheConvert(ING,&retval);
```

3.37 CacheEvalW

Variants: **CacheEvalA**, **CacheEvalH**

```
int CacheEvalW(CACHEWSTRP volatile expr)
```

Arguments

<i>expr</i>	The address of a CACHEWSTR variable.
-------------	--------------------------------------

Description

Evaluates a string as if it were a Caché expression and places the return value in memory for further processing by **CacheType** and **CacheConvert**.

If **CacheEvalW** completes successfully, it sets a flag that allows calls to **CacheType** and **CacheConvert** to complete. These functions are used to process the item returned from **CacheEvalA**.

CAUTION: The next call to **CacheEvalW**, **CacheExecuteW**, or **CacheEnd** will overwrite the existing return value.

Return Values for CacheEvalW

CACHE_CONBROKEN	Connection has been closed due to a serious error condition or RESJOB .
CACHE_ERSYSTEM	Either Caché generated a <SYSTEM> error, or if called from a \$ZF function, an internal counter may be out of sync.
CACHE_NOCON	No connection has been established.
CACHE_STRTOOLONG	String is too long.
CACHE_SUCCESS	String evaluated successfully.

CacheEvalW can also return any of the Caché error codes.

Example

```
int rc;
CACHEWSTR retval;
CACHEWSTR expr;

strcpy(expr.str, "\"Record\"_\"^Recnum\" = \"_$$^GetRec(^Recnum)\");
expr.len = strlen(expr.str);
rc = CacheEvalW(&expr);
if (rc == CACHE_SUCCESS)
    rc = CacheConvert(ING,&retval);
```

3.38 CacheExecuteA

Variants: [CacheExecuteW](#), [CacheExecuteH](#)

```
int CacheExecuteA(CACHE_ASTRP volatile cmd)
```

Arguments

<i>cmd</i>	The address of a CACHE_ASTR variable.
------------	---------------------------------------

Description

Executes the command *string* as if it were typed at the Caché programmer prompt.

CAUTION: The next call to **CacheEvalA**, **CacheExecuteA**, or **CacheEnd** will overwrite the existing return value.

Return Values for CacheExecuteA

CACHE_CONBROKEN	Connection has been closed due to a serious error condition or RESJOB .
CACHE_ERSYSTEM	Either ObjectScript generated a <SYSTEM> error, or if called from a \$ZF function, an internal counter may be out of sync.
CACHE_NOCON	No connection has been established.
CACHE_STRTOOLONG	String is too long.
CACHE_SUCCESS	String executed successfully.

CacheExecuteA can also return any of the Caché error codes.

Example

```
int rc;
CACHE_ASTR command;
sprintf(command.str, "ZN \"USER\""); /* changes namespace */
command.len = strlen(command.str);
rc = CacheExecuteA(&command);
```

3.39 CacheExecuteH

Variants: [CacheExecuteA](#), [CacheExecuteW](#)

```
int CacheExecuteH(CACHEHSTRP volatile cmd)
```

Arguments

<i>cmd</i>	The address of a CACHE_ASTR variable.
------------	---------------------------------------

Description

Executes the command *string* as if it were typed at the Caché programmer prompt.

If **CacheExecuteH** completes successfully, it sets a flag that allows calls to **CacheType** and **CacheConvert** to complete. These functions are used to process the item returned from **CacheEvalH**.

CAUTION: The next call to **CacheEvalH**, **CacheExecuteH**, or **CacheEnd** will overwrite the existing return value.

Return Values for CacheExecuteH

CACHE_CONBROKEN	Connection has been closed due to a serious error condition or RESJOB .
CACHE_ERSYSTEM	Either ObjectScript generated a <SYSTEM> error, or if called from a \$ZF function, an internal counter may be out of sync.
CACHE_NOCON	No connection has been established.
CACHE_STRTOOLONG	String is too long.
CACHE_SUCCESS	String executed successfully.

CacheExecuteH can also return any of the Caché error codes.

Example

```
int rc;
unsigned short zname[] = {'Z', 'N', ' ', ' ', 'U', 'S', 'E', 'R', ' '};
CACHEHSTRP pcommand;
pcommand.str = zname;
pcommand.len = sizeof(zname) / sizeof(unsigned short);
rc = CacheExecuteH(pcommand);
```

3.40 CacheExecuteW

Variants: [CacheExecuteA](#), [CacheExecuteH](#)

```
int CacheExecuteW(CACHEWSTRP volatile cmd)
```

Arguments

<i>cmd</i>	The address of a CACHE_ASTR variable.
------------	---------------------------------------

Description

Executes the command *string* as if it were typed at the Caché programmer prompt.

If **CacheExecuteW** completes successfully, it sets a flag that allows calls to **CacheType** and **CacheConvert** to complete. These functions are used to process the item returned from **CacheEvalW**.

CAUTION: The next call to **CacheEvalW**, **CacheExecuteW**, or **CacheEnd** will overwrite the existing return value.

Return Values for CacheExecuteW

CACHE_CONBROKEN	Connection has been closed due to a serious error condition or RESJOB .
CACHE_ERSYSTEM	Either ObjectScript generated a <SYSTEM> error, or if called from a \$ZF function, an internal counter may be out of sync.
CACHE_NOCON	No connection has been established.
CACHE_STRTOOLONG	String is too long.
CACHE_SUCCESS	String executed successfully.

CacheExecuteW can also return any of the Caché error codes.

Example

```
int rc;
unsigned short zname[] = {'Z','N',' ',' ','U','S','E','R',' '};
CACHEWSTRP pcommand;
pcommand.str = zname;
pcommand.len = sizeof(zname) / sizeof(unsigned short);
rc = CacheExecuteW(pcommand);
```

3.41 CacheExStrKill

```
int CacheExStrKill(CACHE_EXSTRP obj)
```

Arguments

<i>obj</i>	Pointer to the string.
------------	------------------------

Description

Releases the storage associated with an EXSTR string.

Return Values for CacheExStrKill

CACHE_ERUNIMPLEMENTED	String is undefined.
CACHE_SUCCESS	String storage has been released.

3.42 CacheExStrNew

Variants: [CacheExStrNewW](#), [CacheExStrNewH](#)

```
unsigned char * CacheExStrNew(CACHE_EXSTRP zstr, int size)
```

Arguments

<i>zstr</i>	Pointer to a CACHE_EXSTR string descriptor.
<i>size</i>	Number of 8-bit characters to allocate.

Description

Allocates the requested amount of storage for a string, and fills in the EXSTR structure with the length and a pointer to the value field of the structure.

Return Values for CacheExStrNew

Returns a pointer to the allocated string, or NULL if no string was allocated.

3.43 CacheExStrNewW

Variants: [CacheExStrNew](#), [CacheExStrNewH](#)

```
unsigned short * CacheExStrNewW(CACHE_EXSTRP zstr, int size)
```

Arguments

<i>zstr</i>	Pointer to a CACHE_EXSTR string descriptor.
<i>size</i>	Number of 2-byte characters to allocate.

Description

Allocates the requested amount of storage for a string, and fills in the EXSTR structure with the length and a pointer to the value field of the structure.

Return Values for CacheExStrNewW

Returns a pointer to the allocated string, or NULL if no string was allocated.

3.44 CacheExStrNewH

Variants: [CacheExStrNew](#), [CacheExStrNewW](#)

```
unsigned short * CacheExStrNewH(CACHE_EXSTRP zstr, int size)
```

Arguments

<i>zstr</i>	Pointer to a CACHE_EXSTR string descriptor.
<i>size</i>	Number of 4-byte characters to allocate.

Description

Allocates the requested amount of storage for a string, and fills in the EXSTR structure with the length and a pointer to the value field of the structure.

Return Values for CacheExStrNewH

Returns a pointer to the allocated string, or NULL if no string was allocated.

3.45 CacheExtFun

```
int CacheExtFun(unsigned int flags, int nargs)
```

Arguments

<i>flags</i>	Routine flags from CachePushFunc[XW] .
<i>narg</i>	Number of call arguments pushed onto the argument stack.

Description

Performs an extrinsic function call where the return value is pushed onto the argument stack.

Return Values for CacheExtFun

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_FAILURE	Internal consistency error.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.46 CacheGetProperty

```
int CacheGetProperty()
```

Description

Obtains the value of the property defined by **CachePushProperty**. The value is pushed onto the argument stack.

Return Values for CacheGetProperty

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.47 CacheGlobalData

```
int CacheGlobalData(int nargs, int valueflag)
```

Arguments

<i>nargs</i>	Number of call arguments pushed onto the argument stack.
<i>valueflag</i>	Indicates whether the data value, if there is one, should be returned.

Description

Performs a \$Data on the specified global.

Return Values for CacheGlobalData

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_ERPROTECT	Protection violation.
CACHE_ERUNDEF	Node has no associated value.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.48 CacheGlobalGet

```
int CacheGlobalGet(int nargs, int flag)
```

Arguments

<i>narg</i>	Number of subscript expressions pushed onto the argument stack.
<i>flag</i>	Indicates behavior when global reference is undefined: <ul style="list-style-type: none"> 0 — returns CACHE_ERUNDEF 1 — returns CACHE_SUCCESS but the return value is an empty string.

Description

Obtains the value of the global reference defined by **CachePushGlobal** and any subscripts. The node value is pushed onto the argument stack.

Return Values for CacheGlobalGet

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_ERPROTECT	Protection violation.
CACHE_ERUNDEF	Node has no associated value.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.49 CacheGlobalGetBinary

```
int CacheGlobalGetBinary(int numsub, int flag, int *plen, Callin_char_t **pbuf)
```

Arguments

<i>numsub</i>	Number of subscript expressions pushed onto the argument stack.
<i>flag</i>	Indicates behavior when global reference is undefined: <ul style="list-style-type: none"> 0 — returns CACHE_ERUNDEF 1 — returns CACHE_SUCCESS but the return value is an empty string.
<i>plen</i>	Pointer to length of buffer.
<i>pbuf</i>	Pointer to buffer pointer.

Description

Obtains the value of the global reference defined by **CachePushGlobal**[W][H] and any subscripts, and also tests to make sure that the result is a binary string that will fit in the provided buffer. The node value is pushed onto the argument stack.

Return Values for CacheGlobalGetBinary

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_ERPROTECT	Protection violation.
CACHE_ERUNDEF	Node has no associated value.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.50 CacheGlobalIncrement

```
int CacheGlobalIncrement(int narg)
```

Arguments

<i>narg</i>	Number of call arguments pushed onto the argument stack.
-------------	--

Description

Performs a \$INCREMENT and returns the result on top of the stack.

Return Values for CacheGlobalIncrement

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_ERPROTECT	Protection violation.
CACHE_ERUNDEF	Node has no associated value.
CACHE_ERMAXINCR	MAXINCREMENT system error
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.51 CacheGlobalKill

```
int CacheGlobalKill(int narg, int nodeonly)
```

Arguments

<i>narg</i>	Number of call arguments pushed onto the argument stack.
<i>nodeonly</i>	A value of 1 indicates that only the specified node should be killed. When the value is 0, the entire specified global tree is killed.

Description

Performs a ZKILL on a global node or tree.

Return Values for CacheGlobalKill

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_ERPROTECT	Protection violation.
CACHE_ERUNDEF	Node has no associated value.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.52 CacheGlobalOrder

```
int CacheGlobalOrder(int narg, int dir, int valueflag)
```

Arguments

<i>narg</i>	Number of call arguments pushed onto the argument stack.
<i>dir</i>	Direction for the \$Order is 1 for forward, -1 for reverse.
<i>valueflag</i>	Indicates whether the data value, if there is one, should be returned.

Description

Performs a \$Order on the specified global.

Return Values for CacheGlobalOrder

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_ERPROTECT	Protection violation.
CACHE_ERUNDEF	Node has no associated value.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.53 CacheGlobalQuery

```
int CacheGlobalQuery(int nargs, int dir, int valueflag)
```

Arguments

<i>nargs</i>	Number of call arguments pushed onto the argument stack.
<i>dir</i>	Direction for the \$Query is 1 for forward, -1 for reverse.
<i>valueflag</i>	Indicates whether the data value, if there is one, should be returned.

Description

Performs a \$Query on the specified global.

Return Values for CacheGlobalQuery

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_ERPROTECT	Protection violation.
CACHE_ERUNDEF	Node has no associated value.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.54 CacheGlobalRelease

```
int CacheGlobalRelease( )
```

Description

Release ownership of a retained global buffer, if one exists.

Return Values for CacheGlobalRelease

CACHE_SUCCESS	The operation was successful.
---------------	-------------------------------

3.55 CacheGlobalSet

```
int CacheGlobalSet(int narg)
```

Arguments

<i>narg</i>	Number of subscript expressions pushed onto the argument stack.
-------------	---

Description

Stores the value of the global reference defined by **CachePushGlobal** and any subscripts. The node value must be pushed onto the argument stack before this call.

Return Values for CacheGlobalSet

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.56 CacheIncrementCountOref

```
int CacheIncrementCountOref(unsigned int oref)
```

Arguments

<i>oref</i>	Object reference.
-------------	-------------------

Description

Increments the system reference counter for an OREF.

Return Values for CacheIncrementCountOref

CACHE_ERBADOREF	Invalid OREF.
CACHE_SUCCESS	The operation was successful.

3.57 CacheInvokeClassMethod

```
int CacheInvokeClassMethod(int narg)
```

Arguments

<i>narg</i>	Number of call arguments pushed onto the argument stack.
-------------	--

Description

Executes the class method call defined by **CachePushClassMethod[W]** and any arguments. The return value is pushed onto the argument stack.

Return Values for CacheInvokeClassMethod

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.58 CacheInvokeMethod

```
int CacheInvokeMethod(int narg)
```

Arguments

<i>narg</i>	Number of call arguments pushed onto the argument stack.
-------------	--

Description

Executes the instance method call defined by **CachePushMethod[W]** and any arguments pushed onto the argument stack.

Return Values for CacheInvokeMethod

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.59 CacheOflush

```
int CacheOflush()
```

Description

Flushes any pending output.

Return Values for CacheOflush

CACHE_FAILURE	Returns if called from a \$ZF function (rather than from within a Callin executable).
CACHE_SUCCESS	Control function performed.

3.60 CachePop

```
int CachePop(void ** arg)
```

Arguments

<i>arg</i>	Pointer to argument stack entry.
------------	----------------------------------

Description

Pops a value off argument stack.

Return Values for CachePop

CACHE_NORES	No result whose type can be returned has preceded this call.
CACHE_SUCCESS	The operation was successful.

3.61 CachePopCvtH

Variants: [CachePopCvtW](#)

```
int CachePopCvtH(int * lenp, wchar_t ** strp)
```

Arguments

<i>lenp</i>	Pointer to length of string.
<i>strp</i>	Pointer to string pointer.

Description

Pops a local 8-bit string off argument stack and translates it to 4-byte Unicode. Identical to **CachePopStrH** in Unicode environments.

Return Values for CachePopCvtH

CACHE_NORES	No result whose type can be returned has preceded this call.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.

3.62 CachePopCvtW

Variants: [CachePopCvtH](#)

```
int CachePopCvtW(int * lenp, unsigned short ** strp)
```

Arguments

<i>lenp</i>	Pointer to length of string.
<i>strp</i>	Pointer to string pointer.

Description

Deprecated: The long string function [CachePopExStrCvtW](#) should be used for all strings.

Pops a local 8-bit string off argument stack and translates it to 2-byte Unicode. Identical to **CachePopStrW** in Unicode environments.

Return Values for CachePopCvtW

CACHE_NORES	No result whose type can be returned has preceded this call.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.

3.63 CachePopDb1

```
int CachePopDb1(double * nump)
```

Arguments

<i>nump</i>	Pointer to double value.
-------------	--------------------------

Description

Pops a value off argument stack and converts it to a double.

Return Values for CachePopDbl

CACHE_NORES	No result whose type can be returned has preceded this call.
CACHE_SUCCESS	The operation was successful.

3.64 CachePopExStr

Variants: [CachePopExStrW](#), [CachePopExStrH](#)

```
int CachePopExStr(CACHE_EXSTRP sstrp)
```

Arguments

<i>sstrp</i>	Pointer to long string pointer.
--------------	---------------------------------

Description

Pops a value off argument stack and converts it to a string in local 8-bit encoding.

Return Values for CachePopExStr

CACHE_NORES	No result whose type can be returned has preceded this call.
CACHE_SUCCESS	The operation was successful.
CACHE_EXSTR_INUSE	Returned if <i>sstrp</i> has not been initialized to <code>NULL</code> .

3.65 CachePopExStrCvtW

Variants: [CachePopExStrCvtH](#)

```
int CachePopExStrCvtW(CACHE_EXSTRP sstr)
```

Arguments

<i>sstr</i>	Pointer to long string pointer.
-------------	---------------------------------

Description

Pops a local 8-bit string off the argument stack and translates it to a 2-byte Unicode string. On Unicode systems, this is the same as [CachePopExStrW](#).

Return Values for CachePopExStrCvtW

CACHE_NORES	No result whose type can be returned has preceded this call.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.

3.66 CachePopExStrCvtH

Variants: [CachePopExStrCvtW](#)

```
int CachePopExStrCvtW(CACHE_EXSTRP sstr)
```

Arguments

<i>sstr</i>	Pointer to long string pointer.
-------------	---------------------------------

Description

Pops a local 8-bit string off argument stack and translates it to a 4-byte Unicode string. On Unicode systems, this is the same as [CachePopExStrH](#).

Return Values for CachePopExStrCvtH

CACHE_NORES	No result whose type can be returned has preceded this call.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.

3.67 CachePopExStrW

Variants: [CachePopExStr](#), [CachePopExStrH](#)

```
int CachePopExStrW(CACHE_EXSTRP sstrp)
```

Arguments

<i>sstrp</i>	Pointer to long string pointer.
--------------	---------------------------------

Description

Pops a value off argument stack and converts it to a 2-byte Unicode string.

Return Values for CachePopExStrW

CACHE_NORES	No result whose type can be returned has preceded this call.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.
CACHE_EXSTR_INUSE	Returned if <i>sstrp</i> has not been initialized to <code>NULL</code> .

3.68 CachePopExStrH

Variants: [CachePopExStr](#), [CachePopExStrW](#)

```
int CachePopExStrH(CACHE_EXSTRP sstrp)
```

Arguments

<i>sstrp</i>	Pointer to long string pointer.
--------------	---------------------------------

Description

Pops a value off argument stack and converts it to a 4-byte Unicode string.

Return Values for CachePopExStrH

CACHE_NORES	No result whose type can be returned has preceded this call.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.
CACHE_EXSTR_INUSE	Returned if <i>sstrp</i> has not been initialized to <code>NULL</code> .

3.69 CachePopInt

```
int CachePopInt(int* nump)
```

Arguments

<i>nump</i>	Pointer to integer value.
-------------	---------------------------

Description

Pops a value off argument stack and converts it to an integer.

Return Values for CachePopInt

CACHE_NORES	No result whose type can be returned has preceded this call.
CACHE_SUCCESS	The operation was successful.

3.70 CachePopInt64

```
int CachePopInt64(long long * nump)
```

Arguments

<i>nump</i>	Pointer to long long value.
-------------	-----------------------------

Description

Pops a value off argument stack and converts it to a 64-bit (long long) value.

Return Values for CachePopInt64

CACHE_NORES	No result whose type can be returned has preceded this call.
CACHE_SUCCESS	The operation was successful.

3.71 CachePopList

```
int CachePopList(int * lenp, Callin_char_t ** strp)
```

Arguments

<i>lenp</i>	Pointer to length of string.
<i>strp</i>	Pointer to string pointer.

Description

Pops a \$LIST object off argument stack and converts it. String elements are copied or translated as appropriate depending on whether this is a Unicode or 8-bit version.

Return Values for CachePopList

CACHE_NORES	No result whose type can be returned has preceded this call.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.

3.72 CachePopOref

```
int CachePopOref(unsigned int * orefp)
```

Arguments

<i>orefp</i>	Pointer to OREF value.
--------------	------------------------

Description

Pops an OREF off argument stack.

Return Values for CachePopOref

CACHE_NORES	No result whose type can be returned has preceded this call.
CACHE_ERNOOREF	Result is not an OREF.
CACHE_SUCCESS	The operation was successful.

3.73 CachePopPtr

```
int CachePopPtr(void ** ptrp)
```

Arguments

<i>ptrp</i>	Pointer to generic pointer.
-------------	-----------------------------

Description

Pops a pointer off argument stack in internal format.

Return Values for CachePopPtr

CACHE_NORES	No result whose type can be returned has preceded this call.
CACHE_BADARG	The entry is not a valid pointer.
CACHE_SUCCESS	The operation was successful.

3.74 CachePopStr

Variants: [CachePopStrW](#), [CachePopStrH](#)

```
int CachePopStr(int * lenp, Callin_char_t ** strp)
```

Arguments

<i>lenp</i>	Pointer to length of string.
<i>strp</i>	Pointer to string pointer.

Description

Pops a value off argument stack and converts it to a string.

Return Values for CachePopStr

CACHE_NORES	No result whose type can be returned has preceded this call.
CACHE_SUCCESS	The operation was successful.

3.75 CachePopStrH

Variants: [CachePopStr](#), [CachePopStrW](#)

```
int CachePopStrH(int * lenp, wchar_t ** strp)
```

Arguments

<i>lenp</i>	Pointer to length of string.
<i>strp</i>	Pointer to string pointer.

Description

Pops a value off argument stack and converts it to a 4-byte Unicode string.

Return Values for CachePopStrH

CACHE_NORES	No result whose type can be returned has preceded this call.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.

3.76 CachePopStrW

Variants: [CachePopStr](#), [CachePopStrH](#)

```
int CachePopStrW(int * lenp, unsigned short ** strp)
```

Arguments

<i>lenp</i>	Pointer to length of string.
<i>strp</i>	Pointer to string pointer.

Description

Pops a value off argument stack and converts it to a 2-byte Unicode string.

Return Values for CachePopStrW

CACHE_NORES	No result whose type can be returned has preceded this call.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.

3.77 CachePromptA

Variants: [CachePromptW](#), [CachePromptH](#)

```
int CachePromptA(CACHE_ASTRP rbuf)
```

Arguments

<i>rbuf</i>	The prompt string. The minimum length of the returned string is five characters.
-------------	--

Description

Returns a string that would be the programmer prompt (without the “>”).

Return Values for CachePromptA

CACHE_CONBROKEN	Connection has been broken.
CACHE_ERSYSTEM	Either ObjectScript generated a <SYSTEM> error, or if called from a \$ZF function, an internal counter may be out of sync.
CACHE_FAILURE	An unexpected error has occurred.
CACHE_NOCON	No connection has been established.
CACHE_RETTOOSMALL	<i>rbuf</i> must have a length of at least five.
CACHE_SUCCESS	Connection formed.

Example

```
CACHE_ASTR retval;      /* define variable retval */
retval.len = 5;        /* maximum return length of string */
rc = CachePromptA(&retval);
```

3.78 CachePromptH

Variants: [CachePromptA](#), [CachePromptW](#)

```
int CachePromptH(CACHEHSTRP rbuf)
```

Arguments

<i>rbuf</i>	The prompt string. The minimum length of the returned string is five characters.
-------------	--

Description

Returns a string that would be the programmer prompt (without the “>”).

Return Values for CachePromptH

CACHE_CONBROKEN	Connection has been broken.
CACHE_ERSYSTEM	Either ObjectScript generated a <SYSTEM> error, or if called from a \$ZF function, an internal counter may be out of sync.
CACHE_FAILURE	Request failed.
CACHE_NOCON	No connection has been established.
CACHE_RETTOOSMALL	<i>rbuf</i> must have a length of at least five.
CACHE_SUCCESS	Connection formed.

Example

```
CACHEHSTRP retval; /* define variable retval */
retval.len = 5; /* maximum return length of string */
rc = CachePromptH( &retval);
```

3.79 CachePromptW

Variants: [CachePromptA](#), [CachePromptH](#)

```
int CachePromptW(CACHEWSTRP rbuf)
```

Arguments

<i>rbuf</i>	The prompt string. The minimum length of the returned string is five characters.
-------------	--

Description

Returns a string that would be the programmer prompt (without the “>”).

Return Values for CachePromptW

CACHE_CONBROKEN	Connection has been broken.
CACHE_ERSYSTEM	Either ObjectScript generated a <SYSTEM> error, or if called from a \$ZF function, an internal counter may be out of sync.
CACHE_FAILURE	Request failed.
CACHE_NOCON	No connection has been established.
CACHE_RETTOOSMALL	<i>rbuf</i> must have a length of at least five.
CACHE_SUCCESS	Connection formed.

Example

```
CACHEWSTR retval; /* define variable retval */
retval.len = 5; /* maximum return length of string */
rc = CacheConvertW( &retval);
```

3.80 CachePushClassMethod

Variants: [CachePushClassMethodW](#), [CachePushClassMethodH](#)

```
int CachePushClassMethod(int clen, const Callin_char_t * cptr,
                        int mlen, const Callin_char_t * mptr, int flg)
```

Arguments

<i>clen</i>	Class name length (characters).
<i>cptr</i>	Pointer to class name.
<i>mlen</i>	Method name length (characters).
<i>mptr</i>	Pointer to method name.
<i>flg</i>	Specifies whether the method will return a value. If the method returns a value, this flag must be set to 1 in order to retrieve it. The method must return a value via Quit with an argument. Set this parameter to 0 if no value will be returned.

Description

Pushes a class method reference onto the argument stack.

Return Values for CachePushClassMethod

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_BADARG	Invalid call argument.
CACHE_SUCCESS	The operation was successful.

3.81 CachePushClassMethodH

Variants: [CachePushClassMethod](#), [CachePushClassMethodW](#)

```
int CachePushClassMethodH(int clen, const wchar_t * cptr,
                        int mlen, const wchar_t * mptr, int flg)
```

Arguments

<i>clen</i>	Class name length (characters).
<i>cptr</i>	Pointer to class name.
<i>mlen</i>	Method name length (characters).
<i>mptr</i>	Pointer to method name.
<i>flg</i>	Specifies whether the method will return a value. If the method returns a value, this flag must be set to 1 in order to retrieve it. The method must return a value via Quit with an argument. Set this parameter to 0 if no value will be returned.

Description

Pushes a 4-byte Unicode class method reference onto the argument stack.

Return Values for CachePushClassMethodH

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_BADARG	Invalid call argument.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.82 CachePushClassMethodW

Variants: [CachePushClassMethod](#), [CachePushClassMethodH](#)

```
int CachePushClassMethodW(int clen, const unsigned short * cptr,
                        int mlen, const unsigned short * mptr, int flg)
```

Arguments

<i>clen</i>	Class name length (characters).
<i>cptr</i>	Pointer to class name.
<i>mlen</i>	Method name length (characters).
<i>mptr</i>	Pointer to method name.
<i>flg</i>	Specifies whether the method will return a value. If the method returns a value, this flag must be set to 1 in order to retrieve it. The method must return a value via Quit with an argument. Set this parameter to 0 if no value will be returned.

Description

Pushes a 2-byte Unicode class method reference onto the argument stack.

Return Values for CachePushClassMethodW

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_BADARG	Invalid call argument.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.83 CachePushCvtH

Variants: [CachePushCvtW](#)

```
int CachePushCvtH(int len, const wchar_t * ptr)
```

Arguments

<i>len</i>	Number of characters in string.
<i>ptr</i>	Pointer to string.

Description

Translates a Unicode string to local 8-bit and pushes it onto the argument stack. Identical to **CachePushStrH** for Unicode versions.

Return Values for CachePushCvtH

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating the string.

3.84 CachePushCvtW

Variants: [CachePushCvtH](#)

```
int CachePushCvtW(int len, const unsigned short * ptr)
```

Arguments

<i>len</i>	Number of characters in string.
<i>ptr</i>	Pointer to string.

Description

Deprecated: The long string function [CachePushExStrCvtW](#) should be used for all strings.

Translates a Unicode string to local 8-bit and pushes it onto the argument stack. Identical to [CachePushStrW](#) for Unicode versions.

Return Values for CachePushCvtW

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating the string.

3.85 CachePushDb1

```
int CachePushDb1(double num)
```

Arguments

<i>num</i>	Double value.
------------	---------------

Description

Pushes a Caché double onto the argument stack.

Return Values for CachePushDb1

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_SUCCESS	The operation was successful.

3.86 CachePushExStr

Variants: [CachePushExStrW](#), [CachePushExStrH](#)

```
int CachePushExStr(CACHE_EXSTRP sptr)
```

Arguments

<i>sptr</i>	Pointer to the argument value.
-------------	--------------------------------

Description

Pushes a string onto the argument stack.

Return Values for CachePushExStr

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.

3.87 CachePushExStrCvtW

Variants: [CachePushExStrCvtH](#)

```
int CachePushExStrCvtW(CACHE_EXSTRP sptr)
```

Arguments

<i>sptr</i>	Pointer to the argument value.
-------------	--------------------------------

Description

Translates a Unicode string to local 8-bit and pushes it onto the argument stack.

Return Values for CachePushExStrCvtW

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating the string.

3.88 CachePushExStrCvtH

Variants: [CachePushExStrCvtW](#)

```
int CachePushExStrCvtH(CACHE_EXSTRP sptr)
```

Arguments

<i>sptr</i>	Pointer to the argument value.
-------------	--------------------------------

Description

Translates a 4-byte Unicode string to local 8-bit and pushes it onto the argument stack.

Return Values for CachePushExStrCvtH

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating the string.

3.89 CachePushExStrW

Variants: [CachePushExStr](#), [CachePushExStrH](#)

```
int CachePushExStrW(CACHE_EXSTRP sptr)
```

Arguments

<i>sptr</i>	Pointer to the argument value.
-------------	--------------------------------

Description

Pushes a long Unicode string onto the argument stack.

Return Values for CachePushExStrW

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.

3.90 CachePushExStrH

Variants: [CachePushExStr](#), [CachePushExStrW](#)

```
int CachePushExStrH(CACHE_EXSTRP sptr)
```

Arguments

<i>sptr</i>	Pointer to the argument value.
-------------	--------------------------------

Description

Pushes a 4-byte Unicode string onto the argument stack.

Return Values for CachePushExStrH

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.

3.91 CachePushFunc

Variants: [CachePushFuncW](#), [CachePushFuncH](#)

```
int CachePushFunc(unsigned int * rflag, int tlen, const Callin_char_t * tptr,
                 int nlen, const Callin_char_t * nptr)
```

Arguments

<i>rflag</i>	Routine flags for use by CacheExtFun .
<i>tlen</i>	Tag name length (characters), where 0 means that the tag name is null ("").
<i>tptr</i>	Pointer to a tag name. If <i>tlen</i> == 0, then <i>tagptr</i> is unused and (void *) 0 may be used as the pointer value.
<i>nlen</i>	Routine name length (characters), where 0 means that the routine name is null ("") and the current routine name is used.
<i>nptr</i>	Pointer to routine name. If <i>nlen</i> == 0, then <i>nptr</i> is unused and (void *) 0 may be used as the pointer value.

Description

Pushes an extrinsic function reference onto the argument stack.

Return Values for CachePushFunc

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.

3.92 CachePushFuncH

Variants: [CachePushFunc](#), [CachePushFuncW](#)

```
int CachePushFuncH(unsigned int * rflag, int tlen, const wchar_t * tptr,
                  int nlen, const wchar_t * nptr)
```

Arguments

<i>rflag</i>	Routine flags for use by CacheExtFun .
<i>tlen</i>	Tag name length (characters), where 0 means that the tag name is null ("").
<i>tptr</i>	Pointer to a tag name. If <i>tlen</i> == 0, then <i>tptr</i> is unused and (void *) 0 may be used as the pointer value.
<i>nlen</i>	Routine name length (characters), where 0 means that the routine name is null ("") and the current routine name is used.
<i>nptr</i>	Pointer to routine name. If <i>nlen</i> == 0, then <i>nptr</i> is unused and (void *) 0 may be used as the pointer value.

Description

Pushes a 4-byte Unicode extrinsic function reference onto the argument stack.

Return Values for CachePushFuncH

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.93 CachePushFuncW

Variants: [CachePushFunc](#), [CachePushFuncH](#)

```
int CachePushFuncW(unsigned int * rflag, int tlen, const unsigned short * tptr,
                  int nlen, const unsigned short * nptr)
```

Arguments

<i>rflag</i>	Routine flags for use by CacheExtFun .
<i>tlen</i>	Tag name length (characters), where 0 means that the tag name is null ("").
<i>tptr</i>	Pointer to a tag name. If <i>tlen</i> == 0, then <i>tptr</i> is unused and (void *) 0 may be used as the pointer value.
<i>nlen</i>	Routine name length (characters), where 0 means that the routine name is null ("") and the current routine name is used.
<i>nptr</i>	Pointer to routine name. If <i>nlen</i> == 0, then <i>nptr</i> is unused and (void *) 0 may be used as the pointer value.

Description

Pushes a 2-byte Unicode extrinsic function reference onto the argument stack.

Return Values for CachePushFuncW

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.94 CachePushFuncX

Variants: [CachePushFuncXW](#), [CachePushFuncXH](#)

```
int CachePushFuncX(unsigned int * rflag, int tlen, const Callin_char_t * tptr, int off,
                  int elen, const Callin_char_t * eptr,
                  int nlen, const Callin_char_t * nptr)
```

Arguments

<i>rflag</i>	Routine flags for use by CacheExtFun .
<i>tlen</i>	Tag name length (characters), where 0 means that the tag name is null ("").
<i>tptr</i>	Pointer to a tag name. If <i>tlen</i> == 0, then <i>tptr</i> is unused and (void *) 0 may be used as the pointer value.
<i>off</i>	Line offset from specified tag, where 0 means that there is no offset.
<i>elen</i>	Environment name length (characters), where 0 means that there is no environment specified and that the function uses the current environment.
<i>eptr</i>	Pointer to environment name. If <i>elen</i> == 0, then <i>eptr</i> is unused and (void *) 0 may be used as the pointer value.
<i>nlen</i>	Routine name length (characters), where 0 means that the routine name is null ("") and the current routine name is used.
<i>nptr</i>	Pointer to routine name. If <i>nlen</i> == 0, then <i>nptr</i> is unused and (void *) 0 may be used as the pointer value.

Description

Pushes an extended extrinsic function reference onto the argument stack.

Return Values for CachePushFuncX

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.

3.95 CachePushFuncXH

Variants: [CachePushFuncX](#), [CachePushFuncXW](#)

```
int CachePushFuncXH(unsigned int * rflag, int tlen, const wchar_t * tptr, int off,
                   int elen, const wchar_t * eptr, int nlen, const wchar_t * nptr)
```

Arguments

<i>rflag</i>	Routine flags for use by CacheExtFun .
<i>tlen</i>	Tag name length (characters), where 0 means that the tag name is null ("").
<i>tptr</i>	Pointer to a tag name. If <i>tlen</i> == 0, then <i>tptr</i> is unused and (void *) 0 may be used as the pointer value.
<i>off</i>	Line offset from specified tag, where 0 means that there is no offset.
<i>elen</i>	Environment name length (characters), where 0 means that there is no environment specified and that the function uses the current environment.
<i>eptr</i>	Pointer to environment name. If <i>elen</i> == 0, then <i>eptr</i> is unused and (void *) 0 may be used as the pointer value.
<i>nlen</i>	Routine name length (characters), where 0 means that the routine name is null ("") and the current routine name is used.
<i>nptr</i>	Pointer to routine name. If <i>nlen</i> == 0, then <i>nptr</i> is unused and (void *) 0 may be used as the pointer value.

Description

Pushes a 4-byte Unicode extended function routine reference onto the argument stack.

Return Values for CachePushFuncXH

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.96 CachePushFuncXW

Variants: [CachePushFuncX](#), [CachePushFuncXH](#)

```
int CachePushFuncXW(unsigned int * rflag, int tlen, const unsigned short * tptr, int off,
                  int elen, const unsigned short * eptr,
                  int nlen, const unsigned short * nptr)
```

Arguments

<i>rflag</i>	Routine flags for use by CacheExtFun .
<i>tlen</i>	Tag name length (characters), where 0 means that the tag name is null ("").
<i>tptr</i>	Pointer to a tag name. If <i>tlen</i> == 0, then <i>tptr</i> is unused and (void *) 0 may be used as the pointer value.
<i>off</i>	Line offset from specified tag, where 0 means that there is no offset.
<i>elen</i>	Environment name length (characters), where 0 means that there is no environment specified and that the function uses the current environment.
<i>eptr</i>	Pointer to environment name. If <i>elen</i> == 0, then <i>eptr</i> is unused and (void *) 0 may be used as the pointer value.
<i>nlen</i>	Routine name length (characters), where 0 means that the routine name is null ("") and the current routine name is used.
<i>nptr</i>	Pointer to routine name. If <i>nlen</i> == 0, then <i>nptr</i> is unused and (void *) 0 may be used as the pointer value.

Description

Pushes a 2-byte Unicode extended function routine reference onto the argument stack.

Return Values for CachePushFuncXW

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.97 CachePushGlobal

Variants: [CachePushGlobalW](#), [CachePushGlobalH](#)

```
int CachePushGlobal(int nlen, const Callin_char_t * nptr)
```

Arguments

<i>nlen</i>	Global name length (characters).
<i>nptr</i>	Pointer to global name.

Description

Pushes a global reference onto the argument stack.

Return Values for CachePushGlobal

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.

3.98 CachePushGlobalH

Variants: [CachePushGlobal](#), [CachePushGlobalW](#)

```
int CachePushGlobalH(int nlen, const wchar_t * nptr)
```

Arguments

<i>nlen</i>	Global name length (characters).
<i>nptr</i>	Pointer to global name.

Description

Pushes a 4-byte Unicode global reference onto the argument stack.

Return Values for CachePushGlobalH

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.99 CachePushGlobalW

Variants: [CachePushGlobal](#), [CachePushGlobalH](#)

```
int CachePushGlobalW(int nlen, const unsigned short * nptr)
```

Arguments

<i>nlen</i>	Global name length (characters).
<i>nptr</i>	Pointer to global name.

Description

Pushes a 2-byte Unicode global reference onto the argument stack.

Return Values for CachePushGlobalW

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.100 CachePushGlobalX

Variants: [CachePushGlobalXW](#), [CachePushGlobalXH](#)

```
int CachePushGlobalX(int nlen, const Callin_char_t * nptr,
                    int elen, const Callin_char_t * eptr)
```

Arguments

<i>nlen</i>	Global name length (characters).
<i>nptr</i>	Pointer to global name.
<i>elen</i>	Environment name length (characters), where 0 means that there is no environment specified and that the function uses the current environment.
<i>eptr</i>	Pointer to environment name. If <i>elen</i> == 0, then <i>eptr</i> is unused and (void *) 0 may be used as the pointer value.

Description

Pushes an extended global reference onto the argument stack.

Return Values for CachePushGlobalX

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.

3.101 CachePushGlobalXH

Variants: [CachePushGlobalX](#), [CachePushGlobalXW](#)

```
int CachePushGlobalXH(int nlen, const wchar_t * nptr, int elen, const wchar_t * eptr)
```

Arguments

<i>nlen</i>	Global name length (characters).
<i>nptr</i>	Pointer to global name.
<i>elen</i>	Environment name length (characters), where 0 means that there is no environment specified and that the function uses the current environment.
<i>eptr</i>	Pointer to environment name. If <i>elen</i> == 0, then <i>eptr</i> is unused and (void *) 0 may be used as the pointer value.

Description

Pushes a 4-byte Unicode extended global reference onto the argument stack.

Return Values for CachePushGlobalXH

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTAC	String stack overflow.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.102 CachePushGlobalXW

Variants: [CachePushGlobalX](#), [CachePushGlobalXH](#)

```
int CachePushGlobalXW(int nlen, const unsigned short * nptr,
                    int elen, const unsigned short * eptr)
```

Arguments

<i>nlen</i>	Global name length (characters).
<i>nptr</i>	Pointer to global name.
<i>elen</i>	Environment name length (characters), where 0 means that there is no environment specified and that the function uses the current environment.
<i>eptr</i>	Pointer to environment name. If <i>elen</i> == 0, then <i>eptr</i> is unused and (void *) 0 may be used as the pointer value.

Description

Pushes a 2-byte Unicode extended global reference onto the argument stack.

Return Values for CachePushGlobalXW

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTAC	String stack overflow.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.103 CachePushIEEEdbl

```
int CachePushIEEEdbl(double num)
```

Arguments

<i>num</i>	Double value.
------------	---------------

Description

Pushes an IEEE double onto the argument stack.

Return Values for CachePushIEEEdbl

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_SUCCESS	The operation was successful.

3.104 CachePushInt

```
int CachePushInt(int num)
```

Arguments

<i>num</i>	Integer value.
------------	----------------

Description

Pushes an integer onto the argument stack.

Return Values for CachePushInt

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_SUCCESS	The operation was successful.

3.105 CachePushInt64

```
int CachePushInt64(long long num)
```

Arguments

<i>num</i>	long long value.
------------	------------------

Description

Pushes a 64-bit (long long) value onto the argument stack.

Return Values for CachePushInt64

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_SUCCESS	The operation was successful.

3.106 CachePushList

```
int CachePushList(int len, const Callin_char_t * ptr)
```

Arguments

<i>len</i>	Number of characters in string.
<i>ptr</i>	Pointer to string.

Description

Converts a \$LIST object and pushes it onto the argument stack. String elements are copied or translated as appropriate depending on whether this is a Unicode or 8-bit version.

Return Values for CachePushList

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a string element.

3.107 CachePushLock

Variants: [CachePushLockW](#), [CachePushLockH](#)

```
int CachePushLock(int nlen, const Callin_char_t * nptr)
```

Arguments

<i>nlen</i>	Length (in bytes) of lock name.
<i>nptr</i>	Pointer to lock name.

Description

Initializes a [CacheAcquireLock](#) command by pushing the lock name on the argument stack.

Return Values for CachePushLock

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.108 CachePushLockH

Variants: [CachePushLock](#), [CachePushLockW](#)

```
int CachePushLockH(int nlen, const wchar_t * nptr)
```

Arguments

<i>nlen</i>	Length (number of 2–byte or 4–byte characters) of lock name.
<i>nptr</i>	Pointer to lock name.

Description

Initializes a [CacheAcquireLock](#) command by pushing the lock name on the argument stack.

Return Values for CachePushLockH

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.109 CachePushLockW

Variants: [CachePushLock](#), [CachePushLockH](#)

```
int CachePushLockW(int nlen, const unsigned short * nptr)
```

Arguments

<i>nlen</i>	Length (number of 2–byte characters) of lock name.
<i>nptr</i>	Pointer to lock name.

Description

Initializes a [CacheAcquireLock](#) command by pushing the lock name on the argument stack.

Return Values for CachePushLockW

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.110 CachePushLockX

Variants: [CachePushLockXW](#), [CachePushLockXH](#)

```
int CachePushLockX(int nlen, const Callin_char_t * nptr, int elen, const Callin_char_t * eptr)
```

Arguments

<i>nlen</i>	Length (number of 8–bit characters) of lock name.
<i>nptr</i>	Pointer to lock name.
<i>elen</i>	Environment name length (characters), where 0 means that there is no environment specified and that the function uses the current environment. Name must be of the form <Namespace>^[<system>]^<directory>
<i>eptr</i>	Pointer to environment name. If <i>elen</i> == 0, then <i>eptr</i> is unused and (void *) 0 may be used as the pointer value.

Description

Initializes a [CacheAcquireLock](#) command by pushing the lock name and an environment string on the argument stack.

Return Values for CachePushLockX

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.111 CachePushLockXH

Variants: [CachePushLockX](#), [CachePushLockXW](#)

```
int CachePushLockXH(int nlen, const wchar_t * nptr, int elen, const wchar_t * eptr)
```

Arguments

<i>nlen</i>	Length (number of 2–byte or 4–byte characters) of lock name.
<i>nptr</i>	Pointer to lock name.
<i>elen</i>	Environment name length (characters), where 0 means that there is no environment specified and that the function uses the current environment. Name must be of the form <Namespace>^[<system>]^[<directory>
<i>eptr</i>	Pointer to environment name. If <i>elen</i> == 0, then <i>eptr</i> is unused and (void *) 0 may be used as the pointer value.

Description

Initializes a [CacheAcquireLock](#) command by pushing the lock name and an environment string on the argument stack.

Return Values for CachePushLockXH

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.112 CachePushLockXW

Variants: [CachePushLockX](#), [CachePushLockXH](#)

```
int CachePushLockXW(int nlen, const unsigned short * nptr, int elen, const unsigned short * eptr)
```

Arguments

<i>nlen</i>	Length (number of 2-byte characters) of lock name.
<i>nptr</i>	Pointer to lock name.
<i>elen</i>	Environment name length (characters), where 0 means that there is no environment specified and that the function uses the current environment. Name must be of the form <Namespace>^[<system>]^(directory>
<i>eptr</i>	Pointer to environment name. If <i>elen</i> == 0, then <i>eptr</i> is unused and (void *) 0 may be used as the pointer value.

Description

Initializes a [CacheAcquireLock](#) command by pushing the lock name and an environment string on the argument stack.

Return Values for CachePushLockXW

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.113 CachePushMethod

Variants: [CachePushMethodW](#), [CachePushMethodH](#)

```
int CachePushMethod(unsigned int oref, int mlen, const Callin_char_t * mptr, int flg)
```

Arguments

<i>oref</i>	Object reference.
<i>mlen</i>	Method name length (characters).
<i>mptr</i>	Pointer to method name.
<i>flg</i>	Specifies whether the method will return a value. If the method returns a value, this flag must be set to 1 in order to retrieve it. The method must return a value via Quit with an argument. Set this parameter to 0 if no value will be returned.

Description

Pushes an instance method reference onto the argument stack.

Return Values for CachePushMethod

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_BADARG	Invalid call argument.
CACHE_SUCCESS	The operation was successful.

3.114 CachePushMethodH

Variants: [CachePushMethod](#), [CachePushMethodW](#)

```
int CachePushMethodH(unsigned int oref, int mlen, const wchar_t * mptr, int flg)
```

Arguments

<i>oref</i>	Object reference.
<i>mlen</i>	Method name length (characters).
<i>mptr</i>	Pointer to method name.
<i>flg</i>	Specifies whether the method will return a value. If the method returns a value, this flag must be set to 1 in order to retrieve it. The method must return a value via Quit with an argument. Set this parameter to 0 if no value will be returned.

Description

Pushes a 4-byte Unicode instance method reference onto the argument stack.

Return Values for CachePushMethodH

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_BADARG	Invalid call argument.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.115 CachePushMethodW

Variants: [CachePushMethod](#), [CachePushMethodH](#)

```
int CachePushMethodW(unsigned int oref, int mlen, const unsigned short * mptr, int flg)
```

Arguments

<i>oref</i>	Object reference.
<i>mlen</i>	Method name length (characters).
<i>mptr</i>	Pointer to method name.
<i>flg</i>	Specifies whether the method will return a value. If the method returns a value, this flag must be set to 1 in order to retrieve it. The method must return a value via Quit with an argument. Set this parameter to 0 if no value will be returned.

Description

Pushes a 2-byte Unicode instance method reference onto the argument stack.

Return Values for CachePushMethodW

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_BADARG	Invalid call argument.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.116 CachePushOref

```
int CachePushOref(unsigned int oref)
```

Arguments

<i>oref</i>	Object reference.
-------------	-------------------

Description

Pushes an OREF onto the argument stack.

Return Values for CachePushOref

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERBADOREF	Invalid OREF.
CACHE_SUCCESS	The operation was successful.

3.117 CachePushProperty

Variants: [CachePushPropertyW](#), [CachePushPropertyH](#)

```
int CachePushProperty(unsigned int oref, int plen, const Callin_char_t * pptr)
```

Arguments

<i>oref</i>	Object reference.
<i>plen</i>	Property name length (characters).
<i>pptr</i>	Pointer to property name.

Description

Pushes a property reference onto the argument stack.

Return Values for CachePushProperty

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_BADARG	Invalid call argument.
CACHE_SUCCESS	The operation was successful.

3.118 CachePushPropertyH

Variants: [CachePushProperty](#), [CachePushPropertyW](#)

```
int CachePushPropertyH(unsigned int oref, int plen, const wchar_t * pptr)
```

Arguments

<i>oref</i>	Object reference.
<i>plen</i>	Property name length (characters).
<i>pptr</i>	Pointer to property name.

Description

Pushes a 4-byte Unicode property reference onto the argument stack.

Return Values for CachePushPropertyH

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_BADARG	Invalid call argument.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.119 CachePushPropertyW

Variants: [CachePushProperty](#), [CachePushPropertyH](#)

```
int CachePushPropertyW(unsigned int oref, int plen, const unsigned short * pptr)
```

Arguments

<i>oref</i>	Object reference.
<i>plen</i>	Property name length (characters).
<i>pptr</i>	Pointer to property name.

Description

Pushes a 2-byte Unicode property reference onto the argument stack.

Return Values for CachePushPropertyW

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_BADARG	Invalid call argument.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.120 CachePushPtr

```
int CachePushPtr(void * ptr)
```

Arguments

<i>ptr</i>	Generic pointer.
------------	------------------

Description

Pushes a pointer onto the argument stack in internal format.

Return Values for CachePushPtr

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.

3.121 CachePushRtn

Variants: [CachePushRtnW](#), [CachePushRtnH](#)

```
int CachePushRtn(unsigned int * rflag, int tlen, const Callin_char_t * tptr,
                int nlen, const Callin_char_t * nptr)
```

Arguments

<i>rflag</i>	Routine flags for use by CacheDoRtn
<i>tlen</i>	Tag name length (characters), where 0 means that the tag name is null ("").
<i>tptr</i>	Pointer to a tag name. If <i>tlen</i> == 0, then <i>tptr</i> is unused and (void *) 0 may be used as the pointer value.
<i>nlen</i>	Routine name length (characters), where 0 means that the routine name is null ("") and the current routine name is used.
<i>nptr</i>	Pointer to routine name. If <i>nlen</i> == 0, then <i>nptr</i> is unused and (void *) 0 may be used as the pointer value.

Description

Pushes a routine reference onto the argument stack. See [CachePushRtnX](#) for a version that takes all arguments. This is a short form that only takes a tag name and a routine name.

Return Values for CachePushRtn

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.

3.122 CachePushRtnH

Variants: [CachePushRtn](#), [CachePushRtnW](#)

```
int CachePushRtnH(unsigned int * rflag, int tlen, const wchar_t * tptr,
                 int nlen, const wchar_t * nptr)
```

Arguments

<i>rflag</i>	Routine flags for use by CacheDoRtn
<i>tlen</i>	Tag name length (characters), where 0 means that the tag name is null ("").
<i>tptr</i>	Pointer to a tag name. If <i>tlen</i> == 0, then <i>tptr</i> is unused and (void *) 0 may be used as the pointer value.
<i>nlen</i>	Routine name length (characters), where 0 means that the routine name is null ("") and the current routine name is used.
<i>nptr</i>	Pointer to routine name. If <i>nlen</i> == 0, then <i>nptr</i> is unused and (void *) 0 may be used as the pointer value.

Description

Pushes a 4-byte Unicode routine reference onto the argument stack. See [CachePushRtnXH](#) for a version that takes all arguments. This is a short form that only takes a tag name and a routine name.

Return Values for CachePushRtnH

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.123 CachePushRtnW

Variants: [CachePushRtn](#), [CachePushRtnH](#)

```
int CachePushRtnW(unsigned int * rflag, int tlen, const unsigned short * tptr,
                 int nlen, const unsigned short * nptr)
```

Arguments

<i>rflag</i>	Routine flags for use by CacheDoRtn
<i>tlen</i>	Tag name length (characters), where 0 means that the tag name is null ("").
<i>tptr</i>	Pointer to a tag name. If <i>tlen</i> == 0, then <i>tptr</i> is unused and (void *) 0 may be used as the pointer value.
<i>nlen</i>	Routine name length (characters), where 0 means that the routine name is null ("") and the current routine name is used.
<i>nptr</i>	Pointer to routine name. If <i>nlen</i> == 0, then <i>nptr</i> is unused and (void *) 0 may be used as the pointer value.

Description

Pushes a 2-byte Unicode routine reference onto the argument stack. See [CachePushRtnXW](#) for a version that takes all arguments. This is a short form that only takes a tag name and a routine name.

Return Values for CachePushRtnW

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.124 CachePushRtnX

Variants: [CachePushRtnXW](#), [CachePushRtnXH](#)

```
int CachePushRtnX(unsigned int * rflag, int tlen, const Callin_char_t * tptr,
                 int off, int elen, const Callin_char_t * eptr,
                 int nlen, const Callin_char_t * nptr)
```

Arguments

<i>rflag</i>	Routine flags for use by CacheDoRtn
<i>tlen</i>	Tag name length (characters), where 0 means that the tag name is null ("").
<i>tptr</i>	Pointer to a tag name. If <i>tlen</i> == 0, then <i>tptr</i> is unused and (void *) 0 may be used as the pointer value.
<i>off</i>	Line offset from specified tag, where 0 means that there is no offset.
<i>elen</i>	Environment name length (characters), where 0 means that there is no environment specified and that the function uses the current environment.
<i>eptr</i>	Pointer to environment name. If <i>elen</i> == 0, then <i>eptr</i> is unused and (void *) 0 may be used as the pointer value.
<i>nlen</i>	Routine name length (characters), where 0 means that the routine name is null ("") and the current routine name is used.
<i>nptr</i>	Pointer to routine name. If <i>nlen</i> == 0, then <i>nptr</i> is unused and (void *) 0 may be used as the pointer value.

Description

Pushes an extended routine reference onto the argument stack. See [CachePushRtn](#) for a short form that only takes a tag name and a routine name.

Return Values for CachePushRtnX

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.

3.125 CachePushRtnXH

Variants: [CachePushRtnX](#), [CachePushRtnXW](#)

```
int CachePushRtnXH(unsigned int * rflag, int tlen, const wchar_t * tptr,
                  int off, int elen, const wchar_t * eptr,
                  int nlen, const wchar_t * nptr)
```

Arguments

<i>rflag</i>	Routine flags for use by CacheDoRtn
<i>tlen</i>	Tag name length (characters), where 0 means that the tag name is null ("").
<i>tptr</i>	Pointer to a tag name. If <i>tlen</i> == 0, then <i>tptr</i> is unused and (void *) 0 may be used as the pointer value.
<i>off</i>	Line offset from specified tag, where 0 means that there is no offset.
<i>elen</i>	Environment name length (characters), where 0 means that there is no environment specified and that the function uses the current environment.
<i>eptr</i>	Pointer to environment name. If <i>elen</i> == 0, then <i>eptr</i> is unused and (void *) 0 may be used as the pointer value.
<i>nlen</i>	Routine name length (characters), where 0 means that the routine name is null ("") and the current routine name is used.
<i>nptr</i>	Pointer to routine name. If <i>nlen</i> == 0, then <i>nptr</i> is unused and (void *) 0 may be used as the pointer value.

Description

Pushes a 4-byte Unicode extended routine reference onto the argument stack. See [CachePushRtnH](#) for a short form that only takes a tag name and a routine name.

Return Values for CachePushRtnXH

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.126 CachePushRtnXW

Variants: [CachePushRtnX](#), [CachePushRtnXH](#)

```
int CachePushRtnXW(unsigned int * rflag, int tlen, const unsigned short * tptr,
                  int off, int elen, const unsigned short * eptr,
                  int nlen, const unsigned short * nptr)
```

Arguments

<i>rflag</i>	Routine flags for use by CacheDoRtn
<i>tlen</i>	Tag name length (characters), where 0 means that the tag name is null ("").
<i>tptr</i>	Pointer to a tag name. If <i>tlen</i> == 0, then <i>tptr</i> is unused and (void *) 0 may be used as the pointer value.
<i>off</i>	Line offset from specified tag, where 0 means that there is no offset.
<i>elen</i>	Environment name length (characters), where 0 means that there is no environment specified and that the function uses the current environment.
<i>eptr</i>	Pointer to environment name. If <i>elen</i> == 0, then <i>eptr</i> is unused and (void *) 0 may be used as the pointer value.
<i>nlen</i>	Routine name length (characters), where 0 means that the routine name is null ("") and the current routine name is used.
<i>nptr</i>	Pointer to routine name. If <i>nlen</i> == 0, then <i>nptr</i> is unused and (void *) 0 may be used as the pointer value.

Description

Pushes a 2-byte Unicode extended routine reference onto the argument stack. See [CachePushRtnW](#) for a short form that only takes a tag name and a routine name.

Return Values for CachePushRtnXW

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.
Any Caché error	From translating a name.

3.127 CachePushStr

Variants: [CachePushStrW](#), [CachePushStrH](#)

```
int CachePushStr(int len, const Callin_char_t * ptr)
```

Arguments

<i>len</i>	Number of characters in string.
<i>ptr</i>	Pointer to string.

Description

Pushes a byte string onto the argument stack.

Return Values for CachePushStr

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.

3.128 CachePushStrH

Variants: [CachePushStr](#), [CachePushStrW](#)

```
int CachePushStrH(int len, const wchar_t * ptr)
```

Arguments

<i>len</i>	Number of characters in string.
<i>ptr</i>	Pointer to string.

Description

Pushes a 4-byte Unicode string onto the argument stack.

Return Values for CachePushStrH

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.

3.129 CachePushStrW

Variants: [CachePushStr](#), [CachePushStrH](#)

```
int CachePushStrW(int len, const unsigned short * ptr)
```

Arguments

<i>len</i>	Number of characters in string.
<i>ptr</i>	Pointer to string.

Description

Pushes a 2-byte Unicode string onto the argument stack.

Return Values for CachePushStrW

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_ERSTRINGSTACK	String stack overflow.
CACHE_SUCCESS	The operation was successful.

3.130 CachePushUndef

```
int CachePushUndef( )
```

Description

Pushes an Undefined value on the argument stack. The value is interpreted as an omitted function argument.

Return Values for CachePushUndef

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERARGSTACK	Argument stack overflow.
CACHE_SUCCESS	The operation was successful.

3.131 CacheReleaseAllLocks

```
int CacheReleaseAllLocks( )
```

Description

Performs an argumentless Cache LOCK command to remove all locks currently held by the process.

Return Values for CacheReleaseAllLocks

CACHE_SUCCESS	The operation was successful.
---------------	-------------------------------

3.132 CacheReleaseLock

```
int CacheReleaseLock(int nsub, int flg)
```

Arguments

<i>nsub</i>	Number of subscripts in the lock reference.
<i>flg</i>	Modifiers to the lock command. Valid values are one or both of CACHE_IMMEDIATE_RELEASE and CACHE_SHARED_LOCK.

Description

Executes a Cache LOCK command to decrement the lock count for the specified lock name. This command will only release one incremental lock at a time.

Return Values for CacheReleaseLock

CACHE_FAILURE	An unexpected error has occurred.
CACHE_SUCCESS	Successful lock.

3.133 CacheSecureStartA

Variants: [CacheSecureStartW](#), [CacheSecureStartH](#)

```
int CacheSecureStartA(CACHE_ASTRP username, CACHE_ASTRP password, CACHE_ASTRP exename,
                    unsigned long flags, int tout, CACHE_ASTRP prinp, CACHE_ASTRP prout)
```

Arguments

<i>username</i>	Username to authenticate. Use NULL to authenticate as UnknownUser or OS authentication or kerberos credentials cache.
<i>password</i>	Password to authenticate with. Use NULL to authenticate as UnknownUser or OS authentication or kerberos credentials cache.
<i>exename</i>	Callin executable name (or other process identifier). This user-defined string will show up in JOBEXAM and in audit records. NULL is a valid value.
<i>flags</i>	One or more of the terminal settings listed below.
<i>tout</i>	The timeout specified in seconds. Default is 0. If 0 is specified, the timeout will never expire. The timeout applies only to waiting for an available partition, not the time associated with initializing the partition, waiting for internal resources, opening the principal input and output devices, etc.
<i>prinp</i>	String that defines the principal input device for Caché. An empty string (<i>prinp.len</i> == 0) implies using the standard input device for the process. A NULL pointer ((void *) 0) implies using the NULL device.
<i>prout</i>	String that defines the principal output device for Caché. An empty string (<i>prout.len</i> == 0) implies using the standard output device for the process. A NULL pointer ((void *) 0) implies using the NULL device.

Description

Calls into Cache to set up a Cache process..

The input and output devices (*prinp* and *prout*) are opened when this command is executed, not deferred until the first I/O operation. By contrast, normally when you initiate a Caché connection with the cache command, Caché does not open the principal input or output device until it is first used.

Valid values for the *flags* variable are:

- **CACHE_PROGMODE** — Caché should treat the connection as one in Programmer mode, rather than the Application mode. This means that distinct errors are reported to the calling function and the connection remains active. (By default, a Callin connection is like execution of a routine in application mode. Any runtime error detected by Caché results in closing the connection and returning error **CACHE_CONBROKEN** for both the current operation and any subsequent attempts to use Callin without establishing a new connection.)
- **CACHE_TTALL** — Default. Caché should initialize the terminal's settings and restore them across each call into, and return from, the interface.
- **CACHE_TTCALLIN** — Caché should initialize the terminal each time it is called but should restore it only when [CacheEnd](#) is called or the connection is broken.
- **CACHE_TTSTART** — Caché should initialize the terminal when the connection is formed and reset it when the connection is terminated.
- **CACHE_TTNEVER** — Caché should not alter the terminal's settings.

- **CACHE_TTNONE** — Caché should not do any output or input from the principal input/output devices. This is equivalent to specifying the null device for principal input and principal output. **Read** commands from principal input generate an <ENDOFFILE> error and **Write** command to principal output are ignored.
- **CACHE_TTNOUSE** — This flag is allowed with **CACHE_TTALL**, **CACHE_TTCALLIN**, and **CACHE_TTSTART**. It is implicitly set by the flags **CACHE_TTNEVER** and **CACHE_TTNONE**. It indicates that Caché **Open** and **Use** commands are not allowed to alter the terminal, subsequent to the initial open of principal input and principal output.

Return Values for CacheSecureStartA

CACHE_ACCESSDENIED	Authentication has failed. Check the audit log for the real authentication error.
CACHE_ALREADYCON	Connection already existed. Returned if you call CacheSecureStartH from a \$ZF function.
CACHE_CHANGEPASSWORD	Password change required. This return value is only returned if you are using Caché authentication.
CACHE_CONBROKEN	Connection was formed and then broken, and CacheEnd has not been called to clean up.
CACHE_FAILURE	An unexpected error has occurred.
CACHE_STRTOOLONG	<i>prinp</i> or <i>prout</i> is too long.
CACHE_SUCCESS	Connection formed.

The flags parameter(s) convey information about how your C program will behave and how you want Caché to set terminal characteristics. The safest, but slowest, route is to have Caché set and restore terminal settings for each call into ObjectScript. However, you can save ObjectScript overhead by handling more of that yourself, and collecting only information that matters to your program. The parameter **CACHE_TTNEVER** requires the least overhead.

3.134 CacheSecureStartH

Variants: [CacheSecureStartA](#), [CacheSecureStartW](#)

```
int CacheSecureStartH(CACHEHSTRP username, CACHEHSTRP password, CACHEHSTRP exename,
                    unsigned long flags, int tout, CACHEHSTRP prinp, CACHEHSTRP prout)
```

Arguments

<i>username</i>	Username to authenticate. Use NULL to authenticate as UnknownUser or OS authentication or kerberos credentials cache.
<i>password</i>	Password to authenticate with. Use NULL to authenticate as UnknownUser or OS authentication or kerberos credentials cache.
<i>exename</i>	Callin executable name (or other process identifier). This user-defined string will show up in JOBEXAM and in audit records. NULL is a valid value.
<i>flags</i>	One or more of the terminal settings listed below.
<i>tout</i>	The timeout specified in seconds. Default is 0. If 0 is specified, the timeout will never expire. The timeout applies only to waiting for an available partition, not the time associated with initializing the partition, waiting for internal resources, opening the principal input and output devices, etc.
<i>prinp</i>	String that defines the principal input device for Caché. An empty string (<i>prinp.len</i> == 0) implies using the standard input device for the process. A NULL pointer ((void *) 0) implies using the NULL device.
<i>prout</i>	String that defines the principal output device for Caché. An empty string (<i>prout.len</i> == 0) implies using the standard output device for the process. A NULL pointer ((void *) 0) implies using the NULL device.

Description

Calls into Cache to set up a Cache process..

The input and output devices (*prinp* and *prout*) are opened when this command is executed, not deferred until the first I/O operation. By contrast, normally when you initiate a Caché connection with the cache command, Caché does not open the principal input or output device until it is first used.

Valid values for the *flags* variable are:

- **CACHE_PROGMODE** — Caché should treat the connection as one in Programmer mode, rather than the Application mode. This means that distinct errors are reported to the calling function and the connection remains active. (By default, a Callin connection is like execution of a routine in application mode. Any runtime error detected by Caché results in closing the connection and returning error **CACHE_CONBROKEN** for both the current operation and any subsequent attempts to use Callin without establishing a new connection.)
- **CACHE_TTALL** — Default. Caché should initialize the terminal's settings and restore them across each call into, and return from, the interface.
- **CACHE_TTCALLIN** — Caché should initialize the terminal each time it is called but should restore it only when **CacheEnd** is called or the connection is broken.
- **CACHE_TTSTART** — Caché should initialize the terminal when the connection is formed and reset it when the connection is terminated.
- **CACHE_TTNEVER** — Caché should not alter the terminal's settings.
- **CACHE_TTNONE** — Caché should not do any output or input from the principal input/output devices. This is equivalent to specifying the null device for principal input and principal output. **Read** commands from principal input generate an <ENDOFFILE> error and **Write** command to principal output are ignored.
- **CACHE_TTNOUSE** — This flag is allowed with **CACHE_TTALL**, **CACHE_TTCALLIN**, and **CACHE_TTSTART**. It is implicitly set by the flags **CACHE_TTNEVER** and **CACHE_TTNONE**. It indicates that Caché **Open** and **Use** commands are not allowed to alter the terminal, subsequent to the initial open of principal input and principal output.

Return Values for CacheSecureStartH

CACHE_ACCESSDENIED	Authentication has failed. Check the audit log for the real authentication error.
CACHE_ALREADYCON	Connection already existed. Returned if you call CacheSecureStartH from a \$ZF function.
CACHE_CHANGEPASSWORD	Password change required. This return value is only returned if you are using Caché authentication.
CACHE_CONBROKEN	Connection was formed and then broken, and CacheEnd has not been called to clean up.
CACHE_FAILURE	An unexpected error has occurred.
CACHE_STRTOOLONG	<i>prinp</i> or <i>prout</i> is too long.
CACHE_SUCCESS	Connection formed.

The flags parameter(s) convey information about how your C program will behave and how you want Caché to set terminal characteristics. The safest, but slowest, route is to have Caché set and restore terminal settings for each call into ObjectScript. However, you can save ObjectScript overhead by handling more of that yourself, and collecting only information that matters to your program. The parameter `CACHE_TTNEVER` requires the least overhead.

3.135 CacheSecureStartW

Variants: [CacheSecureStartA](#), [CacheSecureStartH](#)

```
int CacheSecureStartW(CACHEWSTRP username, CACHEWSTRP password, CACHEWSTRP exename,
                    unsigned long flags, int tout, CACHEWSTRP prinp, CACHEWSTRP prout)
```

Arguments

<i>username</i>	Username to authenticate. Use NULL to authenticate as UnknownUser or OS authentication or kerberos credentials cache.
<i>password</i>	Password to authenticate with. Use NULL to authenticate as UnknownUser or OS authentication or kerberos credentials cache.
<i>exename</i>	Callin executable name (or other process identifier). This user-defined string will show up in JOBEXAM and in audit records. NULL is a valid value.
<i>flags</i>	One or more of the terminal settings listed below.
<i>tout</i>	The timeout specified in seconds. Default is 0. If 0 is specified, the timeout will never expire. The timeout applies only to waiting for an available partition, not the time associated with initializing the partition, waiting for internal resources, opening the principal input and output devices, etc.
<i>prinp</i>	String that defines the principal input device for Caché. An empty string (<i>prinp.len</i> == 0) implies using the standard input device for the process. A NULL pointer ((void *) 0) implies using the NULL device.
<i>prout</i>	String that defines the principal output device for Caché. An empty string (<i>prout.len</i> == 0) implies using the standard output device for the process. A NULL pointer ((void *) 0) implies using the NULL device.

Description

Calls into Cache to set up a Cache process..

The input and output devices (*prinp* and *prout*) are opened when this command is executed, not deferred until the first I/O operation. By contrast, normally when you initiate a Caché connection with the `cache` command, Caché does not open the principal input or output device until it is first used.

Valid values for the *flags* variable are:

- `CACHE_PROGMODE` — Caché should treat the connection as one in Programmer mode, rather than the Application mode. This means that distinct errors are reported to the calling function and the connection remains active. (By default, a Callin connection is like execution of a routine in application mode. Any runtime error detected by Caché results in closing the connection and returning error `CACHE_CONBROKEN` for both the current operation and any subsequent attempts to use Callin without establishing a new connection.)
- `CACHE_TTALL` — Default. Caché should initialize the terminal's settings and restore them across each call into, and return from, the interface.
- `CACHE_TTCALLIN` — Caché should initialize the terminal each time it is called but should restore it only when **CacheEnd** is called or the connection is broken.
- `CACHE_TTSTART` — Caché should initialize the terminal when the connection is formed and reset it when the connection is terminated.
- `CACHE_TTNEVER` — Caché should not alter the terminal's settings.
- `CACHE_TTNONE` — Caché should not do any output or input from the principal input/output devices. This is equivalent to specifying the null device for principal input and principal output. **Read** commands from principal input generate an `<ENDOFFILE>` error and **Write** command to principal output are ignored.
- `CACHE_TTNOUSE` — This flag is allowed with `CACHE_TTALL`, `CACHE_TTCALLIN`, and `CACHE_TTSTART`. It is implicitly set by the flags `CACHE_TTNEVER` and `CACHE_TTNONE`. It indicates that Caché **Open** and **Use** commands are not allowed to alter the terminal, subsequent to the initial open of principal input and principal output.

Return Values for CacheSecureStartW

<code>CACHE_ACCESSDENIED</code>	Authentication has failed. Check the audit log for the real authentication error.
<code>CACHE_ALREADYCON</code>	Connection already existed. Returned if you call CacheSecureStartH from a \$ZF function.
<code>CACHE_CHANGEPASSWORD</code>	Password change required. This return value is only returned if you are using Caché authentication.
<code>CACHE_CONBROKEN</code>	Connection was formed and then broken, and CacheEnd has not been called to clean up.
<code>CACHE_FAILURE</code>	An unexpected error has occurred.
<code>CACHE_STRTOOLONG</code>	<i>prinp</i> or <i>prout</i> is too long.
<code>CACHE_SUCCESS</code>	Connection formed.

The flags parameter(s) convey information about how your C program will behave and how you want Caché to set terminal characteristics. The safest, but slowest, route is to have Caché set and restore terminal settings for each call into ObjectScript. However, you can save ObjectScript overhead by handling more of that yourself, and collecting only information that matters to your program. The parameter `CACHE_TTNEVER` requires the least overhead.

3.136 CacheSetDir

```
int CacheSetDir(char * dir)
```

Arguments

<i>dir</i>	Pointer to the directory name string.
------------	---------------------------------------

Description

Dynamically sets the name of the manager's directory (CacheSys\Mgr) at runtime. On Windows, the shared library version of Caché requires the use of this function to identify the managers directory for the installation.

Return Values for CacheSetDir

CACHE_FAILURE	Returns if called from a \$ZF function (rather than from within a Callin executable).
CACHE_SUCCESS	Control function performed.

3.137 CacheSetProperty

```
int CacheSetProperty( )
```

Description

Stores the value of the property defined by **CachePushProperty**. The value must be pushed onto the argument stack before this call.

Return Values for CacheSetProperty

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_SUCCESS	The operation was successful.

3.138 CacheSignal

```
int CacheSignal(int signal)
```

Arguments

<i>signal</i>	The operating system's signal value.
---------------	--------------------------------------

Description

Passes on signals caught by user's program to Caché.

This function is very similar to **CacheAbort**, but allows passing of any known signal value from a thread or user side of the connection to the Caché side, for whatever action might be appropriate. For example, this could be used to pass signals intercepted in a user-defined signal handler on to Caché.

Example

```
rc = CacheSignal(CTRL_C_EVENT); // Windows response to Ctrl-C
rc = CacheSignal(CTRL_C_EVENT); // UNIX response to Ctrl-C
```

Return Values for CacheSignal

CACHE_CONBROKEN	Connection has been broken.
CACHE_NOCON	No connection has been established.
CACHE_NOTINCACHE	The Callin partner is not in Caché at this time.
CACHE_SUCCESS	Connection formed.

3.139 CacheSPCReceive

```
int CacheSPCReceive(int * lenp, Callin_char_t * ptr)
```

Arguments

<i>lenp</i>	Maximum length to receive. Modified on return to indicate number of bytes actually received.
<i>ptr</i>	Pointer to buffer that will receive message. Must be at least <i>lenp</i> bytes.

Description

Receive single-process-communication message. The current device must be a TCP device opened in SPC mode, or CACHE_ERFUNCTION will be returned.

Return Values for CacheSPCReceive

CACHE_CONBROKEN	Connection has been closed due to a serious error.
CACHE_NOCON	No connection has been established.
CACHE_ERSYSTEM	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
CACHE_ERFUNCTION	Current device is not TCP device or is not connected.
CACHE_SUCCESS	The operation was successful.

3.140 CacheSPCSend

```
int CacheSPCSend(int len, const Callin_char_t * ptr)
```

Arguments

<i>len</i>	Length of message in bytes.
<i>ptr</i>	Pointer to string containing message.

Description

Send a single-process-communication message. The current device must be a TCP device opened in SPC mode, or `CACHE_ERFUNCTION` will be returned.

Return Values for CacheSPCSend

<code>CACHE_CONBROKEN</code>	Connection has been closed due to a serious error.
<code>CACHE_NOCON</code>	No connection has been established.
<code>CACHE_ERSYSTEM</code>	Either the Caché engine generated a <SYSTEM> error, or Callin detected an internal data inconsistency.
<code>CACHE_ERFUNCTION</code>	Current device is not TCP device or is not connected.
<code>CACHE_ERARGSTACK</code>	Argument stack overflow.
<code>CACHE_ERSTRINGSTACK</code>	String stack overflow.
<code>CACHE_SUCCESS</code>	The operation was successful.
Any Caché error	From translating a name.

3.141 CacheStartA

Variants: [CacheStartW](#), [CacheStartH](#)

```
int CacheStartA(unsigned long flags, int tout, CACHE_ASTRP prinp, CACHE_ASTRP prout)
```

Arguments

<i>flags</i>	One or more of the values listed in the description below.
<i>tout</i>	The timeout specified in seconds. Default is 0. If 0 is specified, the timeout will never expire. The timeout applies only to waiting for an available partition, not the time associated with initializing the partition, waiting for internal resources, opening the principal input and output devices, etc.
<i>prinp</i>	String that defines the principal input device for Caché. An empty string (<i>prinp.len</i> == 0) implies using the standard input device for the process. A NULL pointer ((void *) 0) implies using the NULL device.
<i>prout</i>	String that defines the principal output device for Caché. An empty string (<i>prout.len</i> == 0) implies using the standard output device for the process. A NULL pointer ((void *) 0) implies using the NULL device.

Description

Calls into Caché to set up a Caché process.

The input and output devices (*prinp* and *prout*) are opened when this command is executed, not deferred until the first I/O operation. By contrast, normally when you initiate a Caché connection with the `cache` command, Caché does not open the principal input or output device until it is first used.

Valid values for the *flags* variable are:

- `CACHE_PROGMODE` — Caché should treat the connection as one in Programmer mode, rather than the Application mode. This means that distinct errors are reported to the calling function and the connection remains active. (By default, a Callin connection is like execution of a routine in application mode. Any runtime error detected by Caché results in

closing the connection and returning error `CACHE_CONBROKEN` for both the current operation and any subsequent attempts to use Callin without establishing a new connection.)

- `CACHE_TTALL` — Default. Caché should initialize the terminal's settings and restore them across each call into, and return from, the interface.
- `CACHE_TTCALLIN` — Caché should initialize the terminal each time it is called but should restore it only when **CacheEnd** is called or the connection is broken.
- `CACHE_TTSTART` — Caché should initialize the terminal when the connection is formed and reset it when the connection is terminated.
- `CACHE_TTNEVER` — Caché should not alter the terminal's settings.
- `CACHE_TTNONE` — Caché should not do any output or input from the principal input/output devices. This is equivalent to specifying the null device for principal input and principal output. **Read** commands from principal input generate an `<ENDOFFILE>` error and **Write** command to principal output are ignored.
- `CACHE_TTNOUSE` — This flag is allowed with `CACHE_TTALL`, `CACHE_TTCALLIN`, and `CACHE_TTSTART`. It is implicitly set by the flags `CACHE_TTNEVER` and `CACHE_TTNONE`. It indicates that Caché **Open** and **Use** commands are not allowed to alter the terminal, subsequent to the initial open of principal input and principal output.

Return Values for CacheStartA

<code>CACHE_ALREADYCON</code>	Connection already existed. Returned if you call CacheStartA from a \$ZF function.
<code>CACHE_CONBROKEN</code>	Connection was formed and then broken, and CacheEndA has not been called to clean up.
<code>CACHE_FAILURE</code>	An unexpected error has occurred.
<code>CACHE_STRTOOLONG</code>	<i>prinp</i> or <i>prout</i> is too long.
<code>CACHE_SUCCESS</code>	Connection formed.

The flags parameter(s) convey information about how your C program will behave and how you want Caché to set terminal characteristics. The safest, but slowest, route is to have Caché set and restore terminal settings for each call into ObjectScript. However, you can save ObjectScript overhead by handling more of that yourself, and collecting only information that matters to your program. The parameter `CACHE_TTNEVER` requires the least overhead.

Example

A Caché process is started. The terminal is reset after each interface Callin function. The start fails if a partition is not allocated within 20 seconds. The file `dobackup` is used for input. It contains an ObjectScript script for a Caché backup. Output appears on the terminal.

```

CACHE_ASTR inpdev;
CACHE_ASTR outdev;
int rc;

strcpy(inpdev.str, "[BATCHDIR]dobackup");
inpdev.len = strlen(inpdev.str);
strcpy(outdev.str, "");
outdev.len = strlen(outdev.str);
rc = CacheStartA(CACHE_TTALL|CACHE_TTNOUSE, 0, inpdev, outdev);

```

3.142 CacheStartH

Variants: [CacheStartA](#), [CacheStartW](#)

```
int CacheStartH(unsigned long flags,int tout,CACHEHSTRP prinp,CACHEHSTRP prout)
```

Arguments

<i>flags</i>	One or more of the values listed in the description below.
<i>tout</i>	The timeout specified in seconds. Default is 0. If 0 is specified, the timeout will never expire. The timeout applies only to waiting for an available partition, not the time associated with initializing the partition, waiting for internal resources, opening the principal input and output devices, etc.
<i>prinp</i>	String that defines the principal input device for Caché. An empty string (<i>prinp.len</i> == 0) implies using the standard input device for the process. A NULL pointer ((void *) 0) implies using the NULL device.
<i>prout</i>	String that defines the principal output device for Caché. An empty string (<i>prout.len</i> == 0) implies using the standard output device for the process. A NULL pointer ((void *) 0) implies using the NULL device.

Description

Calls into Caché to set up a Caché process.

The input and output devices (*prinp* and *prout*) are opened when this command is executed, not deferred until the first I/O operation. By contrast, normally when you initiate a Caché connection with the `cache` command, Caché does not open the principal input or output device until it is first used.

Valid values for the *flags* variable are:

- `CACHE_PROGMODE` — Caché should treat the connection as one in Programmer mode, rather than the Application mode. This means that distinct errors are reported to the calling function and the connection remains active. (By default, a Callin connection is like execution of a routine in application mode. Any runtime error detected by Caché results in closing the connection and returning error `CACHE_CONBROKEN` for both the current operation and any subsequent attempts to use Callin without establishing a new connection.)
- `CACHE_TTALL` — Default. Caché should initialize the terminal's settings and restore them across each call into, and return from, the interface.
- `CACHE_TTCALLIN` — Caché should initialize the terminal each time it is called but should restore it only when **CacheEnd** is called or the connection is broken.
- `CACHE_TTSTART` — Caché should initialize the terminal when the connection is formed and reset it when the connection is terminated.
- `CACHE_TTNEVER` — Caché should not alter the terminal's settings.
- `CACHE_TTNONE` — Caché should not do any output or input from the principal input/output devices. This is equivalent to specifying the null device for principal input and principal output. **Read** commands from principal input generate an `<ENDOFFILE>` error and **Write** command to principal output are ignored.
- `CACHE_TTNOUSE` — This flag is allowed with `CACHE_TTALL`, `CACHE_TTCALLIN`, and `CACHE_TTSTART`. It is implicitly set by the flags `CACHE_TTNEVER` and `CACHE_TTNONE`. It indicates that Caché **Open** and **Use** commands are not allowed to alter the terminal, subsequent to the initial open of principal input and principal output.

Return Values for CacheStartH

CACHE_ALREADYCON	Connection already existed. Returned if you call CacheStartH from a \$ZF function.
CACHE_CONBROKEN	Connection was formed and then broken, and CacheEndH has not been called to clean up.
CACHE_FAILURE	An unexpected error has occurred.
CACHE_STRTOOLONG	<i>prinp</i> or <i>prout</i> is too long.
CACHE_SUCCESS	Connection formed.

The flags parameter(s) convey information about how your C program will behave and how you want Caché to set terminal characteristics. The safest, but slowest, route is to have Caché set and restore terminal settings for each call into ObjectScript. However, you can save ObjectScript overhead by handling more of that yourself, and collecting only information that matters to your program. The parameter `CACHE_TTNEVER` requires the least overhead.

Example

A Caché process is started. The terminal is reset after each interface Callin function. The start fails if a partition is not allocated within 20 seconds. The file `dobackup` is used for input. It contains an ObjectScript script for a Caché backup. Output appears on the terminal.

```
inpdev;
outdev;
int rc;

strcpy(inpdev.str, "[BATCHDIR]dobackup");
inpdev.len = strlen(inpdev.str);
strcpy(outdev.str, "");
outdev.len = strlen(outdev.str);
rc = CacheStartH(CACHE_TTALL|CACHE_TTNOUSE, 0, inpdev, outdev);
```

3.143 CacheStartW

Variants: [CacheStartA](#), [CacheStartH](#)

```
int CacheStartW(unsigned long flags, int tout, CACHEWSTRP prinp, CACHEWSTRP prout)
```

Arguments

<i>flags</i>	One or more of the values listed in the description below.
<i>tout</i>	The timeout specified in seconds. Default is 0. If 0 is specified, the timeout will never expire. The timeout applies only to waiting for an available partition, not the time associated with initializing the partition, waiting for internal resources, opening the principal input and output devices, etc.
<i>prinp</i>	String that defines the principal input device for Caché. An empty string (<i>prinp.len</i> == 0) implies using the standard input device for the process. A NULL pointer ((void *) 0) implies using the NULL device.
<i>prout</i>	String that defines the principal output device for Caché. An empty string (<i>prout.len</i> == 0) implies using the standard output device for the process. A NULL pointer ((void *) 0) implies using the NULL device.

Description

Calls into Caché to set up a Caché process.

The input and output devices (*prinp* and *prout*) are opened when this command is executed, not deferred until the first I/O operation. By contrast, normally when you initiate a Caché connection with the `cache` command, Caché does not open the principal input or output device until it is first used.

Valid values for the *flags* variable are:

- `CACHE_PROGMODE` — Caché should treat the connection as one in Programmer mode, rather than the Application mode. This means that distinct errors are reported to the calling function and the connection remains active. (By default, a Callin connection is like execution of a routine in application mode. Any runtime error detected by Caché results in closing the connection and returning error `CACHE_CONBROKEN` for both the current operation and any subsequent attempts to use Callin without establishing a new connection.)
- `CACHE_TTALL` — Default. Caché should initialize the terminal's settings and restore them across each call into, and return from, the interface.
- `CACHE_TTCALLIN` — Caché should initialize the terminal each time it is called but should restore it only when **CacheEnd** is called or the connection is broken.
- `CACHE_TTSTART` — Caché should initialize the terminal when the connection is formed and reset it when the connection is terminated.
- `CACHE_TTNEVER` — Caché should not alter the terminal's settings.
- `CACHE_TTNONE` — Caché should not do any output or input from the principal input/output devices. This is equivalent to specifying the null device for principal input and principal output. **Read** commands from principal input generate an `<ENDOFFILE>` error and **Write** command to principal output are ignored.
- `CACHE_TTNOUSE` — This flag is allowed with `CACHE_TTALL`, `CACHE_TTCALLIN`, and `CACHE_TTSTART`. It is implicitly set by the flags `CACHE_TTNEVER` and `CACHE_TTNONE`. It indicates that Caché **Open** and **Use** commands are not allowed to alter the terminal, subsequent to the initial open of principal input and principal output.

Return Values for CacheStartW

<code>CACHE_ALREADYCON</code>	Connection already existed. Returned if you call CacheStartW from a \$ZF function.
<code>CACHE_CONBROKEN</code>	Connection was formed and then broken, and CacheEndW has not been called to clean up.
<code>CACHE_FAILURE</code>	An unexpected error has occurred.
<code>CACHE_STRTOOLONG</code>	<i>prinp</i> or <i>prout</i> is too long.
<code>CACHE_SUCCESS</code>	Connection formed.

The flags parameter(s) convey information about how your C program will behave and how you want Caché to set terminal characteristics. The safest, but slowest, route is to have Caché set and restore terminal settings for each call into ObjectScript. However, you can save ObjectScript overhead by handling more of that yourself, and collecting only information that matters to your program. The parameter `CACHE_TTNEVER` requires the least overhead.

Example

A Caché process is started. The terminal is reset after each interface Callin function. The start fails if a partition is not allocated within 20 seconds. The file `dobackup` is used for input. It contains an ObjectScript script for a Caché backup. Output appears on the terminal.

```
inpdev;
outdev;
int rc;

strcpy(inpdev.str, "[BATCHDIR]dobackup");
inpdev.len = strlen(inpdev.str);
strcpy(outdev.str, "");
outdev.len = strlen(outdev.str);
rc = CacheStartW(CACHE_TTALL|CACHE_TTNOUSE,0,inpdev,outdev);
```

3.144 CacheTCommit

```
int CacheTCommit( )
```

Description

Executes a Cache TCommit command.

Return Values for CacheTCommit

CACHE_SUCCESS	TCommit was successful.
---------------	-------------------------

3.145 CacheTLevel

```
int CacheTLevel( )
```

Description

Returns the current nesting level (\$TLEVEL) for transaction processing.

Return Values for CacheTLevel

CACHE_SUCCESS	TLevel was successful.
---------------	------------------------

3.146 CacheTRollback

```
int CacheTRollback(int nlev)
```

Arguments

<i>nlev</i>	Determines how many levels to roll back, (all levels if 0, one level if 1).
-------------	---

Description

Executes a Cache TRollback command. If *nlev* is 0, rolls back all transactions in progress (no matter how many levels of TSTART were issued) and resets \$TLEVEL to 0. If *nlev* is 1, rolls back the current level of nested transactions (the one initiated by the most recent TSTART) and decrements \$TLEVEL by 1.

Return Values for CacheTRollback

CACHE_SUCCESS	TStart was successful.
---------------	------------------------

3.147 CacheTStart

```
int CacheTStart( )
```

Description

Executes a Cache TStart command.

Return Values for CacheTStart

CACHE_SUCCESS	TStart was successful.
---------------	------------------------

3.148 CacheType

```
int CacheType( )
```

Description

Returns the native type of the item returned by **CacheEvalA**, **CacheEvalW**, or **CacheEvalH** as the function value.

Return Values for CacheType

CACHE_ASTRING	8-bit string.
CACHE_CONBROKEN	Connection has been closed due to a serious error condition or RESJOB .
CACHE_DOUBLE	64-bit Caché floating point.
CACHE_ERSYSTEM	Either ObjectScript generated a <SYSTEM> error, or if called from a \$ZF function, an internal counter may be out of sync.
CACHE_IEEE_DBL	64-bit IEEE floating point.
CACHE_INT	32-bit integer.
CACHE_NOCON	No connection has been established.
CACHE_NORES	No result whose type can be returned (no call to CacheEvalA or CacheEvalW preceded this call).
CACHE_OREF	Caché object reference.
CACHE_WSTRING	Unicode string.

Example

```
rc = CacheType();
```

3.149 CacheUnPop

```
int CacheUnPop( )
```

Description

Restores the stack entry from **CachePop**.

Return Values for CacheUnPop

CACHE_NORES	No result whose type can be returned has preceded this call.
CACHE_SUCCESS	The operation was successful.